

UniTerm® Payment Interface Application

UniTerm Integration and Deployment Guide

Revision: 8.0.1

Publication date September 28, 2015

UniTerm Integration and Deployment Guide

Main Street Softworks, Inc.

Revision: 8.0.1

Publication date September 28, 2015

Copyright © 2015 Main Street Softworks, Inc.

Legal Notice

The information contained herein is provided *As Is* without warranty of any kind, express or implied, including but not limited to, the implied warranties of merchantability and fitness for a particular purpose. There is no warranty that the information or the use thereof does not infringe a patent, trademark, copyright, or trade secret.

Main Street Softworks, Inc. shall not be liable for any direct, special, incidental, or consequential damages resulting from the use of any information contained herein, whether resulting from breach of contract, breach of warranty, negligence, or otherwise, even if Main Street has been advised of the possibility of such damages. Main Street reserves the right to make changes to the information contained herein at anytime without notice. No part of this document may be reproduced or transmitted in any form or by any means, electronic or mechanical, for any purpose, without the express written permission of Main Street Softworks, Inc.

Table of Contents

1. Revision History	1
2. UniTerm System	2
2.1. Overview	2
2.2. UniTerm Architecture	2
2.3. Design Decisions	3
3. UniTerm Integration and Deployment Overview	4
3.1. Deployment	4
3.2. Versioning	4
3.2.1. Version Scheme	4
3.2.2. Wildcard Versioning	5
3.3. Licensing	5
3.3.1. Registration	5
3.3.2. Device Definition	5
3.3.3. Management	6
3.4. Starting UniTerm	6
3.4.1. Command Line Options	6
3.5. Multiple Instances	6
3.6. Swapping Devices	7
3.7. Configuration Files	7
3.7.1. Location	8
3.7.2. Parameters	8
3.8. Communication	10
3.8.1. Network Communication	10
3.8.2. Android Service Communication	10
3.9. Shutting Down UniTerm	10
3.10. Required User Permissions	11
4. UniTerm Protocol	12
4.1. Overview	12
4.2. UniTerm Request Parameters	12
4.3. UniTerm Response Parameters	16
4.4. UniTerm Error Codes	17
5. EMV transactions with UniTerm	19
5.1. Transaction Flow and Prompting	19
5.1.1. Swipe prompts to insert	19
5.1.2. Tap prompts to insert	19
5.1.3. Insert prompts to swipe	19
5.1.4. PIN required on Credit Cards	20
5.1.5. Signature not requested	20
5.1.6. Tap transaction run as MSR on chip card, no insert requested	20
5.1.7. Immediate decline without contacting the processor	20
5.2. Common questions	20
5.2.1. How do I add a gratuity/tip to a transaction?	20
6. UniTerm Protocol Examples	22
6.1. EMV Transaction [device load]	22
6.1.1. Uniterm Request Data	22
6.1.2. Uniterm Response Data	22

6.2. EMV Transaction [Interac]	23
6.2.1. Uniterm Request Data	23
6.2.2. Uniterm Response Data	23
6.3. Pin Debit (forced) Transaction Request	24
6.3.1. Uniterm Request Data	24
6.3.2. GUI output	25
6.3.3. Uniterm Response Data	25
7. UniTerm Test Application	26
8. UniTerm Code Examples	27
9. UniTerm Point of Interaction Devices	28
9.1. Supported POI Devices	28
9.1.1. Ingenico RBA information	29
9.1.2. Verifone VX XPI information	32
9.1.3. Ingenico CPX/uCPX information	32
10. Certifications and Device Configurations	34
10.1. Certification List	34
10.2. Configuration Definitions	35
A. UniTerm Device Loading	37
B. EMV Receipt Requirements	39
B.1. Receipt content	39
B.1.1. Base receipt content	39
B.2. Receipt Data Returned by UniTerm	40
B.3. Receipt Data NOT Returned by UniTerm	43
B.4. Signature Line Requirements	44
B.5. Merchant vs Customer Copy	44
B.6. Moneris Requirements	45
B.7. Receipt Examples	45
B.7.1. EMV Insert, Signature Required	45
B.7.2. EMV Insert, PIN Verified	49
B.7.3. EMV Insert, No CVM	52
B.7.4. EMV Insert, Card Decline	55
B.7.5. EMV Insert, Card Removed (Decline)	57
B.7.6. EMV Insert, Interac	59
B.7.7. EMV Contactless, Interac Flash Decline	62
B.7.8. EMV Contactless, Decline	64
C. UniTerm Code Examples	66
C.1. Microsoft C# using libmonetra	66
C.2. Microsoft C# using XML and HttpWebRequest	70
C.3. Java using libmonetra	75
C.4. PHP using libmonetra	79
C.5. Microsoft VB.Net using libmonetra	84
C.6. Microsoft VBScript using XML and MSXML2	88
C.7. Microsoft Visual Basic 6 using libmonetra	92
D. PCI Security and Implementation	97

1 Revision History

Version	Date	Changes
v8.0.1	2015-09-28	<ul style="list-style-type: none">• Re-word and clarify configuration information for Ingenico RBA• Clarify fields can be sent in to pre-populate key entry fields in GUI mode.• Receipt should show "CALL ISSUER" for a response code of "CALL".• Cardholder Name on receipts can be printed under the signature line.• Document how to configure an RBA device for contactless.• Remove unused <code>monetra_host</code> and <code>monetra_port</code> variables in example code.• Add touchscreen mode support via <code>[uniterm]</code> config option of <code>guimode=touchscreen</code>.• SSL is no longer a valid communication option for Android. Only Service communication is allowed.• Add <code>ssl_auth_key</code> and <code>ssl_auth_cert</code> configuration parameters for the <code>[monetra]</code> section.• Add <code>ssl_cert_validate</code> configuration parameter for the <code>[monetra]</code> section.• Add <code>ssl_cadir</code> configuration parameter for the <code>[monetra]</code> section.• Verifone recommended XPI version updated to 8.24D.• Ingenico recommended RBA version updated to 15.06.• Ingenico RBA added support for USB-HID.• Update receipt examples to the latest generated by UniTerm Tester.
v8.0.0	2015-08-17	<ul style="list-style-type: none">• Initial revision

2 UniTerm System


2.1. Overview	2
2.2. UniTerm Architecture	2
2.3. Design Decisions	3

2.1 Overview

UniTerm securely handles sensitive cardholder data independent of the merchants application software. In addition, UniTerm provides a simple consistent interface to multiple payment acceptance devices such as card readers, pinpads and terminals.

2.2 UniTerm Architecture

The UniTerm module is accessed via its 'Transaction Request' mode, as described below:



A	Point of sale application calls UniTerm for txnrequest (such as a sale transaction request) and includes basic information such as the amount of the sale and an order-number.
B	UniTerm communicates with devices (such as pinpads and card readers) to retrieve sensitive data, depending on request type (step A).

C	UniTerm sends the full transaction data-set to the Monetra server for further processing.
D	The Monetra server processes the transaction request (such as a sale) against the appropriate end point (for example TSYS) and then sends back the response it receives to the UniTerm module.
E	The UniTerm module then returns the transaction response back to the calling application.

2.3 Design Decisions

UniTerm is designed to run as an independent application running in a separate address space from any integrated applications. The design decisions behind this are due to the PCI PA-DSS and EMV certification requirements. If UniTerm was designed as a library rather than a separate application, it would be considered part of the integrator's application. This would mandate that integrators validate to PCI PA-DSS as well as go through direct end-to-end EMV brand certifications.

UniTerm's goal is to assist integrators in avoiding the costly and time consuming validations and certifications. While it would have been easier to implement as a library, and easier for integrators to use if it was a library, we strongly believe that the benefits far outweigh the integration and deployment inconveniences.

3 UniTerm Integration and Deployment Overview

3.1. Deployment	4
3.2. Versioning	4
3.2.1. Version Scheme	4
3.2.2. Wildcard Versioning	5
3.3. Licensing	5
3.3.1. Registration	5
3.3.2. Device Definition	5
3.3.3. Management	6
3.4. Starting UniTerm	6
3.4.1. Command Line Options	6
3.5. Multiple Instances	6
3.6. Swapping Devices	7
3.7. Configuration Files	7
3.7.1. Location	8
3.7.2. Parameters	8
3.8. Communication	10
3.8.1. Network Communication	10
3.8.2. Android Service Communication	10
3.9. Shutting Down UniTerm	10
3.10. Required User Permissions	11

3.1 Deployment

For Desktop deployments, Uniterm should be bundled and distributed with the POS system.

Provided to each integrator is a license for UniTerm that is installed via the Monetra Installer, however, production deployments will not use this distribution mechanism. Instead, integrators should package the directory that is created after installation to distribute with their own package (e.g. POS). The UniTerm directory is self-contained and can be relocated to any path the integrator sees fit without any additional system dependencies as long as the paths for any sub-directories included with the UniTerm installation (if applicable) are kept in the same relative paths in relation to the UniTerm executable.

For Android deployments, Uniterm is available as a standalone APK package. It can also be bundled with the POS system, please contact us for guidance on bundling.

3.2 Versioning

3.2.1 Version Scheme

The versioning scheme employed by UniTerm is formatted as `x.y.z`, where each `x`, `y`, and `z` components are numeric-only version indicators separated by a period. Each numeric component may be from one to three digits in length. All software distribution updates will result in at least one of the components being updated.

The x component of the version indicates the product major version number. The major version component only changes when there are significant feature changes, or the changes impact any part of a security standard, such as PCI PA-DSS.

The y component of the version indicates a product minor version change. The minor version will change when there are minor feature enhancements that do not impact the part of any security standard such as PCI PA-DSS.

The z component of the version indicates a bug-fix release. Bug-fix releases do not change the overall feature-set or functionality of UniTerm, but may include security related fixes such as updates to 3rd party libraries (e.g. cryptographic libraries) distributed with UniTerm.

3.2.2 Wildcard Versioning

PCI PA-DSS requires a specific wildcard versioning definition which corresponds to the release which is being validated for compliance. With this release of UniTerm, the official wildcard versioning is 8 . y . z. The major (x) version number component is fixed at 8, which as per the versioning definition states there will be no major feature changes or changes which impact the PCI PA-DSS standard (e.g. all changes that do not affect the major version number are classified as "no impact" changes). The minor (y) and bug-fix (z) wildcard components comply with the descriptions in the previous section.

Any future change which results in a change to the major version number will have a corresponding PCI PA-DSS validation.

3.3 Licensing

All Uniterm licensing is managed at the server level by the Monetra system with which Uniterm is connected. Since licensing is administered at the server level, there is nothing unique that needs to be deployed with Uniterm on the client side (such as a license or certificate file).

3.3.1 Registration

Uniterm generates unique ids for each connected device in order to send to Monetra to track the number of UniTerm licenses in use.

When Uniterm is started, during the first transaction and every 24hrs thereafter, the unique device ID will be automatically registered with Monetra. If this device is already associated with a UniTerm license, the license meta-data will be updated. If the device is not currently associated with a UniTerm license, Monetra will register this unique device id if a UniTerm license slot is available, otherwise Monetra will reject the registration request and Uniterm will cancel the transaction.

3.3.2 Device Definition

A device is either a physical Point of Interaction device, or a Graphical User Interface of the computer in which Uniterm is running.

Each physical device will consume a UniTerm license, the license is tied to the device serial number. Since the license is tied to the device, the physical device may be transferred to different POS stations without consuming additional licensing.

The use of the GUI mode in Uniterm, whether used with keyboard emulation card readers, for acceptance of manually keyed card entry, or even simply used for Clerk status feedback, will also consume a UniTerm license.

3.3.3 Management

Since UniTerm licensing is managed at the Monetra server, all license administration (view licenses, delete licenses, etc) can be performed using either the Monetra Administrator GUI or via the Monetra API. To more easily help identify and manage licenses, additional data is available in the license list such as: initial creation timestamp, last used timestamp, last used username, device type, and device serial number.



Note: If a UniTerm license (device or GUI) is removed (de-registered) from Monetra, then the license slot is not eligible to be re-used for 7 days. However, if the same [deleted] device is re-presented, it can immediately re-consume the license slot.

3.4 Starting UniTerm

For Desktop based deployments, the UniTerm module must be launched by the POS application software and should not be started at startup. If the POS system does not start Uniterm, then it is possible Uniterm will not be able to obtain screen focus for on-screen prompts.

For Android deployments, Uniterm should be automatically started at Boot, and simply Binding to the already-running service is sufficient.

3.4.1 Command Line Options

When starting UniTerm for Desktop based deployments, there are a few command line options supported that control the behavior.

- `-c` - Full path to the `ini` file to read. If not specified, it searches for the `uniterm.ini` in the paths documented in Section 3.7.
- `-p` - Port for UniTerm to listen on for incoming connections. If not specified, the value in the `ini` file is used. The purpose of this configuration value is to aid in the ability to start multiple UniTerm instances on the same machine with the intention of using GUI mode for multiple user logins (e.g. Terminal Services).
- `-h` - Help options are displayed.

3.5 Multiple Instances

When running UniTerm in conjunction with Citrix or Terminal Services, with the intention of using GUI mode, it is necessary to start multiple instances of UniTerm on the same

machine. This can be accomplished by using a different port for each UniTerm instance. The port can either be configured via the command line options or by specifying a different UniTerm `ini` file. The integrated application would then communicate with UniTerm on its own dedicated port to prevent interference with any other UniTerm instances. The dedicated UniTerm instance must still be started by the POS application in that user instance otherwise UniTerm will be unable to display information or prompts.

If using UniTerm in device-only mode, it is recommended to use only a single instance of UniTerm and not start multiple instances. UniTerm is designed to be able to handle multiple transactions across multiple devices without the need for additional instances.

3.6 Swapping Devices

From time to time it may be necessary to swap out devices, whether the device is malfunctioning, being updated to a new firmware load, or simply being relocated. When a device is swapped, UniTerm needs to be made aware of this, otherwise there could be unexpected behavior. In order to reduce transaction latency as much as possible, the first time a device is used after a fresh UniTerm start, UniTerm performs many queries against the device which may take many seconds to complete. These queries gather device information such as its type and capabilities and ensure the proper configuration parameters are loaded. In extreme cases this first transaction may detect a full device load is necessary which could extend this time to many minutes and result in a device reboot. On all subsequent transactions, these initial steps are stored in an in-memory cache and will not be repeated unless UniTerm is explicitly told to do so. When a device is swapped out, UniTerm may have no way to know this has occurred since it is operating on this cached data.

In order to tell UniTerm that a device has been swapped out, simply send a `u_action=device-load` request or restart UniTerm. Either of these actions will force UniTerm to clear its in-memory cache and connect to the device as if it was the first transaction.

In some cases if the device itself isn't swapped (so the serial number has not changed), but instead the device has been manually cleared, such as when performing a firmware update, additional steps may need to be taken to ensure EMV parameters are loaded. There may be no way for UniTerm to determine if the device has the latest EMV parameters so UniTerm caches the `loadid` associated with the device serial number in the `uniterm.ini`. If this on-disk cache is incorrect because the device was manipulated outside of UniTerm, UniTerm must be informed of this by passing `u_forceload=yes` with the `u_action=device-load` request. The `u_forceload` will tell UniTerm to ignore the `loadid` cache forcibly loading the EMV parameters into the device. In fact, it may be prudent to explicitly use `u_forceload` any time a device is swapped to ensure all data is loaded into the device.

3.7 Configuration Files

There is a single configuration file named `uniterm.ini` that must be configured before UniTerm can be used. The `uniterm.ini` MUST be readable and writable by the UniTerm process.

3.7.1 Location

The location of the `uniterm.ini` may vary from system to system, and the default search paths, listed in priority order, are:

- Windows:
 - `%APPDATA%/Uniterm/uniterm.ini`
 - same path as the `monetra_uniterm.exe` executable
- Mac OS X:
 - `~/Library/Application Support/Uniterm/uniterm.ini`
- Linux/Unix:
 - `~/.uniterm/uniterm.ini`
 - same path as the `monetra_uniterm` executable



Note: If the `uniterm.ini` cannot be located, or does not have proper read and write access, UniTerm will still start listening on the default port 8123 and return an `INI` related `u_errorcode` on all requests with a description of the issue. It should be noted that once the error has been corrected, UniTerm must be restarted to clear the error condition to force UniTerm to re-read its `INI` file.

3.7.2 Parameters

The parameters in this section are in standard `ini` format grouped by sections. Sections are in the format of "[section]". The settings for each section are in key/value pair format of "key=value".

3.7.2.1 Section: [monetra]

- `host`: Required. Hostname/address where Monetra resides
- `port`: Required. Port to connect to Monetra on
- `ssl_cert_validate`: Optional. Controls validation of the Monetra SSL server certificate. Possible Values are:
 - `full` - validate server certificate signature and require the full domain matches the certificate
 - `fuzzy` - validate server certificate signature and only the base domain matches the certificate
 - `validate` - validate only the server certificate signature, do not validate the domain name in the certificate
 - `none` - perform no server certificate validationIf no value is specified, defaults to `none`. Monetra, by default, deploys a self-signed SSL certificate. You must either explicitly deploy a signed certificate (signed by a trusted CA) with Monetra to be able to turn on certificate validation, or add Monetra's self-signed SSL certificate to the trust list (see `ssl_cadir`).
- `ssl_cadir`: Optional. Path to a directory containing a list of the PEM-encoded trusted SSL Certificate Authority roots. If not specified, will use the `caroots` directory contained in the

same path relative to the UniTerm executable. Only used when `ssl_cert_validate` is set to a value other than `none`.

- `ssl_auth_key`: Optional. Path to the SSL client certificate key used for two factor authentication. If not specified, the server will not be able to validate the authenticity of the client, however most deployments will not utilize this level of verification. Must be specified if `ssl_auth_cert` is specified.
- `ssl_auth_cert`: Optional. Path to the SSL client certificate used for two factor authentication. If not specified, the server will not be able to validate the authenticity of the client, however most deployments will not utilize this level of verification. Must be specified if `ssl_auth_key` is specified.

3.7.2.2 Section: [uniterm]

3.7.2.2.1 Operating Parameters

- `port`: Required on all except Android. Port to listen on for incoming connections.
- `sharedsecret`: Optional. The value specified is the shared secret to use for the communication protocol. A value must be set if one wishes to allow remote connections (along with `localonly=no`), or to enable the `MODIFYCONFIG` command. When this configuration parameter is set, all requests to UniTerm must include the `u_sharedsecret` protocol-level key/value pair set to the same value.
- `localonly`: Optional. If not specified, defaults to `yes`. If set to `no`, a `sharedsecret` must also be set and remote connections will be allowed.
- `ssl_cert`: Optional. If not specified attempts to locate `ssl.crt` in the same path as `uniterm.ini`
- `ssl_key`: Optional. If not specified attempts to locate `ssl.key` in the same path as `uniterm.ini`

3.7.2.2.2 Feature Parameters

- `idle_message`: Optional. Set the default idle message displayed on any device when not processing a transaction. This can be overwritten on a per-device level using the `u_deviceidlemessage` parameter in the protocol. This is not supported on all devices.
- `unsupportedcard`: Optional. If not specified, defaults to `no`. If set to `yes`, this allows trackdata to be returned to the caller for `txnrequest` and `cardrequest` only when the card type is confirmed to be non-financial. This is to allow in-store private-label gift (on `txnrequest`) as well as manager cards. The card must be returned unencrypted from the reader to be supported.
- `nosigfloor`: Optional. If not specified, defaults to disabled, should be specified as a dollar amount. This configuration value is a temporary stop-gap until Monetra supports advertising a merchant's desired floor limit for requiring signatures and will be removed in the future. This only applies to Swiped transactions as EMV follows chip-specific rules. For instance if

the value is set to 50.00, and a 40.00 authorization is attempted as a swipe transaction, they will NOT be prompted to sign, however a 60.00 authorization would be prompted to sign.

- `guimode`: Valid options are `normal` and `touchscreen`. If not specified, defaults to `normal`. `TouchScreen` mode enlarges all text in dialogs and provides an on-screen keypad to be used for manual card entry. Only numeric input is allowed in `touchscreen` mode, if an alpha-numeric Postal code needs to be entered (such as for Canada), a keyboard must be used. `Normal` mode is designed for use at a workstation with a keyboard and mouse.

3.8 Communication

The communication protocol for Uniterm is very similar to that of Monetra. At the heart of the protocol is a simple key/value pair message structure, very similar to the Monetra Client Interface Protocol Specification. In fact, some of these key/value pairs sent to Uniterm are simply passed-through to Monetra for processing.

When communicating with Uniterm, you use standard network communications, except on Android where you have the option to use Service-based communication (network-communication is available as a configurable option).

3.8.1 Network Communication

Uniterm supports both raw SSL communication with key/value pair transport, or XML over HTTPS. The protocol being used is autodetected by Uniterm on the first message sent by the POS. The standard APIs used with Monetra are also able to be used with Uniterm as they simply facilitate the same key/value pair transport mechanisms as the raw protocols. For more information on the underlying communications protocols or APIs, please reference the communications documentation and API documentation for Monetra.

Normally, Uniterm listens on localhost (127.0.0.1) via IPv4 on port 8123. It is recommended to use the ip address rather than 'localhost' since some operating systems may not fall back to trying IPv4. However, it is possible to make Uniterm accept connections from remote machines by configuring a `'sharedsecret='` set to a desired value as well as `'localonly=no'` in the `uniterm.ini`. When a shared secret is configured, all requests to Uniterm must include the shared secret in order to prevent malicious requests.

3.8.2 Android Service Communication

The Android Service communication option utilizes AIDL in order to transmit the key/value pairs for each request to the Uniterm Service. Please see our Android SDK for an example of how to utilize this communication option.

3.9 Shutting Down UniTerm

Uniterm should only be shut down if it was started by the POS, and does not apply to Android systems. On Windows, a standard Window shutdown message may be sent, or on Unix a `SIGTERM` signal may be sent to the Uniterm process. Or universally Uniterm supports a shutdown message via its protocol.

3.10 Required User Permissions

The Monetra user identified by the username must be a Monetra SUB-USER with the `obscure_sensitive_data` flag set. For pass-through operations the subuser must have additional permissions for the transaction types it will perform (such as 'sale').

Uniterm also requires these permissions to operate:

- CHKPWD
- MERCHINFO
- GETPERMS
- SALE
- VOID
- REVERSAL
- IMAGEADD
- TERMLOAD - EMV or INTERAC ONLY
- EMVCOMPLETE - EMV ONLY
- INTERACMAC - Canadian Interac Debit Only

More permissions may be required based on the POS operations supported.

4 UniTerm Protocol

4.1. Overview	12
4.2. UniTerm Request Parameters	12
4.3. UniTerm Response Parameters	16
4.4. UniTerm Error Codes	17

4.1 Overview

Application software communicates with the UniTerm module via the UniTerm protocol (which is similar to the Monetra Client Interface Protocol).

4.2 UniTerm Request Parameters

The table below describes the parameters used within the UniTerm protocol.

PARAMETER	VALUE
username	The Monetra username to authenticate as. For security reasons this should be a restricted subuser account.
password	The Monetra password associated with username.
u_action	<p>DEVICELoad. Load a device with EMV and/or Interac parameters. This request will start a terminal download of EMV and/or Interac parameters to load into the device being used. Requires username, password, u_device, and u_devicetype parameters. If the load for the device is identical to the previous load, the load will be skipped. Please note this process may take up to 3 or 4 minutes depending on the processing institution being used and the device being used. The Device may also reboot during this process. It is strongly recommended to call this function when a lane opens, however if it is not called, it will automatically be performed prior to the first transaction. If the device or merchant account does not support EMV or Interac, this command will simply return success. Optionally u_deviceidlemessage may be passed to this as well to set the device's default message if supported by the device.</p> <p>TXNREQUEST Transaction Request. Sensitive data (trackdata, account, cvv, avs, pin) will be retrieved by the UniTerm module either via the GUI or via a card entry device and forwarded to the Monetra server.</p> <p>CARDREQUEST Non-Financial Card Entry Request. UniTerm will prompt for card entry, and if it is determined the card is non-financial, it will return the card data. This can be used for manager cards and private label gift cards</p>

that are not processed through Monetra. The card must be swiped, and the reader must be configured to return the card in unencrypted form.

PASSTHROUGH This action performs a direct pass-through of parameters to the Monetra server. Only the username, password, and u_action parameters are required. Can be used for reports, etc.

CANCEL Will attempt to cancel an outstanding TXNREQUEST. Requires 'username', 'password' and 'u_id' fields which must match the pending request. If the transaction cannot be canceled, such as if it is ineligible (such as when waiting on a response from the Monetra server), or the device doesn't support canceling the outstanding request, u_errorcode will return PENDING_TRAN.

DEVICETYPES Will return a comma separated list of device types supported by the UniTerm module. No authentication required.

Headers:

- devicetype - internal device name
- manufacturer - textual description of device manufacturer
- model - textual description of model
- connectivity - pipe separated list of connectivity methods supported by the device, e.g. SERIAL|USB|BLUETOOTH|IP
- functionality - pipe separated list of functionality supported by the device:

e.g. SIGNATURE|SWIPE|RESET|IDLE|REQKEY|REQPIN

STATUS Requests the current status of a pending TXNREQUEST. Requires 'username', 'password' and 'u_id' fields which must match the pending request. This will provide a textual verbiage response suitable for clerk display.

SERIALLIST Will return a comma separated list of all serial ports enumerated on the system. No authentication required.

Headers:

- port - The port path
- desc - Description of port, if applicable

	<p>BLUETOOTHLIST List all 'bluetooth' devices that have been paired with the machine UniTerm is running on. The device may or may not be present. Currently only supported on Android.</p> <p>Headers:</p> <ul style="list-style-type: none"> • name - The textual name of the device as registered with the operating system. • mac - The device bluetooth MAC address • uuid - The device bluetooth UUID <p>USBLIST List all supported USB devices that are currently attached to the machine UniTerm is running on.</p> <p>Headers:</p> <ul style="list-style-type: none"> • nickname - The devicetype (device internal name) associated with the USB entry • devpath - The device path of the USB device (windows only) • bus - The USB bus (linux only) • addr - The USB address (linux only) • vendorID - The USB vendor id • productID - The USB product id • serial_number - The device serial number (if provided) <p>SHUTDOWN Terminates execution of the UniTerm module. This should be called when the application software terminates.</p> <p>MODIFYCONFIG Allows a select number of ini configuration settings to be set via the API. In order to activate the ability to use this feature, an integrator must enable the shared secret in the configuration and the connection must come from the local machine.</p> <p>VERSION Requests the current version of UniTerm. The version information is output in human-readable format in the verbiage response field. The version information also contains the build number.</p>
u_flags	<p>Txnrequest and Cardrequest only. Multiple flags may be sent per data ticket request. All flags are separated by a pipe () symbol.</p> <ul style="list-style-type: none"> • ENCRYPTEDONLY - Permit encrypted reader data only. Not valid on cardrequest • DEVICEONLY - Suppresses display of clerk facing dialog. For instance, on a swipe request, no swipe dialog would be presented. Important note: keyboard emulation readers

	<p>are not supported with this flag, only serial, USB HID, and Bluetooth devices can work. On Android, this flag is automatically implied due to the fact that it does not support a GUI mode of operation.</p> <ul style="list-style-type: none"> • KEY - Perform capture of manually keyed data. Not valid on cardrequest. If an account or expdate field is passed in on the request to UniTerm, the fields will be pre-populated in GUI mode. • AVS - Request AVS data. Only allowed on keyed transactions. If a street or zip field is passed in on the request to UniTerm, the fields will be pre-populated in GUI mode. • CVV - Request for CVV data. Only allowed on keyed transactions.
u_cardclass	<p>Txnrequest only. Optional. The card class that is expected (this provides a hint much like flags) to enforce only this card classification be allowed. Uniterm will normally prompt for the card type from the cardholder if it can not be determined based on the card presented. This option can be useful if the POS has already determined the card type prior to requesting Uniterm to process a transactions. If a card is presented that does not match the card class, the transaction will be rejected. Supported classes are:</p> <ul style="list-style-type: none"> • CREDIT - Credit card transaction • DEBIT - DEBIT card transaction • EBT - Electronic Benefits transaction • INTERAC - Canadian Interac card transaction • GIFT - Gift card transaction
u_device	<p>Txnrequest, Cardrequest, and DeviceLoad only. This specifies the path of the card entry device. Required parameter unless performing a GUI-based action (such as manual keyed entry, or swiping via a keyboard emulation card reader). Required if u_devicetype is provided.</p> <ul style="list-style-type: none"> • USB • SER:port - Serial • BT:mac,[uuid] - Bluetooth • IP:ipaddr:port - IP
u_devicetype	<p>Txnrequest, Cardrequest, and DeviceLoad only. The unique device type supported by Uniterm as found via a devicelist request. Required if u_device is provided.</p>
u_language	<p>Txnrequest only. Used to override terminal defaults for display of text prompts. Current choices are "en" or "fr".</p>
u_currency	<p>Txnrequest only. The numeric ISO currency code for EMV transactions (e.g. 840 for USD, 124 for CAD). Defaults to</p>

	the terminals configured currency. This parameter is used to override the terminals default currency.
<code>u_deviceidlemessage</code>	Txnrequest or deviceload only. Sets a message that the terminal should display when idle, this will be persistently cached by UniTerm and associated with the device serial number.
<code>u_forceload</code>	deviceload only. Values allowed are yes, no, and full. If not specified defaults to no. A value of yes will force a reload of all EMV parameters even if UniTerm believes the device already has the latest set of parameters. A value of full will additionally force reloading of all other objects UniTerm maintains, including but not limited to, configuration values, forms, and images.
<code>u_id</code>	Txnrequest, Cardrequest, Status, and Cancel only. A unique id (generated by the calling application) that identifies the transaction. This is used for checking the status or canceling the transaction. Without this id the transaction state cannot be queried.
<code>amount</code>	Txnrequest only. Transaction amount. Required.
<code>u_sharedsecret</code>	Required on all transactions if a shared secret is set in the ini file.
<code>monetra/host</code>	Modifyconfig only. Modify the [monetra] host configuration value.
<code>monetra/port</code>	Modifyconfig only. Modify the [monetra] port configuration value.
<code>uniterm/idle_message</code>	Modifyconfig only. Modify the [uniterm] idle_message configuration value.

4.3 UniTerm Response Parameters

The UniTerm module will return all standard response tags from the Monetra server such as `code=`, `cardtype=`, and so on. The additional tags listed below are for transaction flow handling, please see the EMV Receipt section for additional tags that may be returned specific to receipt formatting.

PARAMETER	VALUE
<code>u_emv_chip_malfunction</code>	(yes or not sent) = Indicates that there was a chip malfunction during EMV Complete. Note: Certain card brands require a note on the receipt stating there was a chip malfunction.
<code>u_need_signature</code>	(yes or not sent) = Monetra returns <code>rcpt_emv_cvm</code> which can have a value of "sig" saying sig is required. The <code>u_need_signature</code> means that a signature is required and it should be printed/obtained from the paper receipt. If an EMV requires a signature and one was not captured

	electronically, this flag indicates it should be obtained via a paper receipt.
u_errorcode	See section below.
u_cancelable	u_action=status only. Yes or No. Indicates if the current transaction state will allow a cancel to be sent. This is useful for showing and hiding a cancel button within an integration's GUI.
trackdata	u_action is txnrequest or cardrequest only. Also requires the ini configuration of unsupportedcard=yes. Will only be returned for non-financial cards that are returned unencrypted from the reader. Facilitates the use of manager cards as well as in-store private label gift systems that do not flow through Monetra. The u_errorcode returned with the response will always be NONFINANCIAL. Support during a txnrequest is tailored to the use of private label gift cards and will only be returned when the cardholder selects GIFT from the payment type selection screen.

4.4 UniTerm Error Codes

Errors will be returned in the **u_errorcode** field. Each error code may be used for more than one error type. Please see the verbiage response for more details. Note: On a successful transaction the **u_errorcode** will be set to SUCCESS but that only indicates communications with the Monetra server were successful. It does not mean the transaction was approved.

u_errorcode	definition
MISSING_PARAM	A required parameter was missing.
INVALID_PARAM	A specified parameter was invalid
PENDING_TRAN	pending transaction already in progress
INVALID_USE	Typically means parameters specified should not have been specified together.
PERMISSION_ERROR	The user account within Monetra was misconfigured.
MONETRA_ERROR	There was an error communicating with Monetra.
DEVICE_ERROR	There was an error communicating with the card entry device.
CANCELED	User canceled request
FAILURE	Generic Failure
DEVICE_INUSE	The device specified is being used by another transaction.
BAD_READ	The device returned a card read error.
MAC_FAILURE	The transaction was rejected because the MAC returned from the processor did not match the expected value.
EMV_CARD_DENY	The card locally declined the transaction.

EMV_CARD_REMOVED	The card was removed before the end of the transaction.
CARD_NOT_SUPPORTED	The card presented was not supported.
DEVICE_NOT_LOADED	The device needs to be loaded before it can run EMV transactions.
FALLBACK_NOTALLOWED	There was an error reading the chip and the card brand rule does not allow the card to be re-presented via another means.
INI_CANNOT_FIND	The uniterm.ini could not be found.
INI_CANNOT_READ	The uniterm.ini is not readable by the Uniterm process.
INI_CANNOT_WRITE	The uniterm.ini is not writable by the Uniterm process.
INI_INVALID_PARAM	The uniterm.ini has an invalid configuration parameter.
NONFINANCIAL	The card presented is not a financial card. This code will be returned when requesting and returning trackdata for non-financial cards when the configuration of unsupportedcard=yes is set.

5 EMV transactions with UniTerm

5.1. Transaction Flow and Prompting	19
5.1.1. Swipe prompts to insert	19
5.1.2. Tap prompts to insert	19
5.1.3. Insert prompts to swipe	19
5.1.4. PIN required on Credit Cards	20
5.1.5. Signature not requested	20
5.1.6. Tap transaction run as MSR on chip card, no insert requested	20
5.1.7. Immediate decline without contacting the processor	20
5.2. Common questions	20
5.2.1. How do I add a gratuity/tip to a transaction?	20

EMV transactions, by nature, are much more complex than traditional magnetic stripe transactions. Uniterm hides this complexity from the application software. In the case of magnetic stripe and EMV transaction, the application software will send the request to Uniterm. The device capabilities (EMV for example) will be determined by Uniterm, along with the merchant account configuration. From these Uniterm will handle the appropriate prompting and flow aspects related to the determined capabilities. The application software simply needs to send a `u_action=TXNREQUEST` and let Uniterm handle the rest.

5.1 Transaction Flow and Prompting

Integrators unfamiliar with EMV may notice some specific flow cases that seem counter-intuitive at first. This section is meant to address these EMV-specific cases.

5.1.1 Swipe prompts to insert

If a chip-enabled card is swiped on an EMV-capable terminal, it is mandated that the user be prompted to insert the card. This is an EMV certification requirement which cannot be lifted and it is meant to train consumers to insert their cards and to prevent fraud.

5.1.2 Tap prompts to insert

There are certain thresholds negotiated between the card and terminal which may request a chip-enabled card that is presented as a tap transaction be inserted instead. When this occurs, it can be due to a number of factors including fraud mitigation, or the card has determined it needs to be updated (for insert transactions, an issuer can choose to return issuer scripts to remotely reprogram cards).

5.1.3 Insert prompts to swipe

If a chip-enabled card is prompted to be swiped, this is usually an indication that there was a chip malfunction and the cardholder should have their card replaced, called a technical fallback. It is expected at some point in the future, technical fallback will be disallowed due to

fraud concerns. The other possibility is if the application id in use by the card is not supported by the terminal.

5.1.4 PIN required on Credit Cards

The cardholder verification method is negotiated between the card and the terminal. If both the card and terminal support PIN entry, it may be chosen as the desired verification method. Consumers in the US may not expect to enter a PIN on their credit cards, but it is common among foreign cards.

5.1.5 Signature not requested

The cardholder verification method is negotiated between the card and the terminal. They may negotiate Signature, PIN, or what is called `NOCV` which means no cardholder verification is required for the transaction. The decision is strictly made based on the terminal capabilities and card capabilities.

5.1.6 Tap transaction run as MSR on chip card, no insert requested

It is a requirement by the card brands that if a chip-capable card is presented as a tap that the card NOT be prompted for insertion. This can happen due to a terminal not being configured for contactless EMV support, or if a chip is malfunctioning.

5.1.7 Immediate decline without contacting the processor

EMV cards have the ability to make decisions about the transaction before it is even processed. From time to time a merchant may see a chip card presented that results in an immediate decline before requesting cardholder verification or connecting to a processing institution. This could happen because the card has exceeded some internal threshold, or the card has received a remote script on a previous transaction to explicitly block transactions, such as a card block or application block.

5.2 Common questions

5.2.1 How do I add a gratuity/tip to a transaction?

Tips are added to EMV authorizations just as they are with MSR authorizations, nothing has changed in the US rules. An integrator will simply send a `preauth` with the order amount, then when the tip amount is known, a `preauthcomplete` will be sent with the final order amount and `examount` will contain the tip amount. However, if the tip is greater than 20%, merchants should obtain a new authorization for the tip according to the card brand rules. Of course if the tip amount is known prior to the authorization, the tip amount should be included a part of the authorization request.

There is much confusion regarding tips in the US market with the introduction of EMV Chip and Pin, most of this is due to European rules which state the gratuity amount must be sent with the initial authorization request. This does NOT apply to the US market.

Please refer to the below card brand documentation for more information:

- http://www.mastercard.com/us/merchant/pdf/TPR-Entire_Manual_public.pdf (page 70)
- <http://usa.visa.com/download/merchants/play-it-smart-with-chip-payment-transactions.pdf> (page 3)

6 UniTerm Protocol Examples

6.1. EMV Transaction [device load]	22
6.1.1. Uniterm Request Data	22
6.1.2. Uniterm Response Data	22
6.2. EMV Transaction [Interac]	23
6.2.1. Uniterm Request Data	23
6.2.2. Uniterm Response Data	23
6.3. Pin Debit (forced) Transaction Request	24
6.3.1. Uniterm Request Data	24
6.3.2. GUI output	25
6.3.3. Uniterm Response Data	25

Several examples are provided below which describe how to use the UniTerm protocol.

6.1 EMV Transaction [device load]

6.1.1 Uniterm Request Data

PARAMETER	VALUE
password	test123
u_action	deviceload
u_device	USB
u_deviceidlemessage	WELCOME
u_devicetype	ingenico_cpx
u_flags	DEVICEONLY
u_id	1182112391
username	moneris_ipp320x:sub

6.1.2 Uniterm Response Data

PARAMETER	VALUE
addltermcaps	F000F0F001
addltermcaps_desired	6000F0F001
addltermcaps_loa	F000F0A001
altered_termload	yes
code	AUTH
loa_id	3C
termcaps	E0B8C8
termcaps_desired	E0B8C8

termcaps_loa	E0B8C8
termtype	22
termtype_desired	21
u_errorcode	SUCCESS
verbiage	Device loaded

6.2 EMV Transaction [Interac]

6.2.1 Uniterm Request Data

PARAMETER	VALUE
action	sale
amount	1.00
nsf	yes
ordernum	899065992
password	test123
u_action	txnrequest
u_device	USB
u_deviceidlemessage	WELCOME
u_devicetype	ingenico_cpx
u_flags	DEVICEONLY
u_id	899065992
username	moneris_ipp320x:sub

6.2.2 Uniterm Response Data

PARAMETER	VALUE
account	XXXXXXXXXXXXXXXXX2145
auth	221093
batch	1
cardholdername	Test Card 14
cardtype	INTERAC
code	AUTH
item	793
language	en
merch_addr1	123 STREET NAME
merch_addr2	CITY, STATE ZIP

merch_id	1625
merch_name	MERCHANT NAME
merch_phone	(888) 555-1234
msoft_code	INT_SUCCESS
pclevel	0
phard_code	SUCCESS
rcpt_acct_type	checking
rcpt_custom	refnum:660136000010017930
rcpt_emv_ac	882D8427A268E214
rcpt_emv_actype	TC
rcpt_emv_aid	A0000002771010
rcpt_emv_cvm	pin
rcpt_emv_name	Interac
rcpt_emv_tsi	7800
rcpt_emv_tvr	8000008000
rcpt_entry_mode	C
rcpt_host_ts	072315151022
rcpt_issuer_resp_code	00
rcpt_resp_code	001
timestamp	1437678622
ttid	992
u_errorcode	SUCCESS

6.3 Pin Debit (forced) Transaction Request

6.3.1 Uniterm Request Data

PARAMETER	VALUE
action	sale
amount	1.00
nsf	yes
ordernum	899065992
password	test123
u_action	txnrequest
u_cardclass	DEBIT
u_device	USB
u_deviceidlemessage	WELCOME

u_devicetype	ingenico_rba
u_id	899065992
username	transarmor_isc250:sub

6.3.2 GUI output



6.3.3 Uniterm Response Data

PARAMETER	VALUE
account	XXXXXXXXXXXX0027
auth	412303
batch	15
cardtype	MCDEBIT
code	AUTH
item	139
merch_id	0993
msoft_code	INT_SUCCESS
pclevel	0
phard_code	SUCCESS
rcpt_entry_mode	S
timestamp	1437678765
ttid	200
u_errorcode	SUCCESS

7 UniTerm Test Application

Included with the UniTerm software distribution is a test application known as "Uniterm Tester". This test application is a simple graphical user interface which may be used to test the various functionality in UniTerm. This utility should be used by developers exploring the functionality of Uniterm as it will provide the request and response messages from UniTerm as well as generate sample receipts for each request. The test utility can be found in the same directory as the `monetra_uniterm` executable named `unitermtester`.

8 UniTerm Code Examples

Code examples are provided help you understand how easy it is to integrate your application with the UniTerm middleware. Please see Appendix C for complete code examples.

Examples are provided for the following languages:

- Microsoft C# using libmonetra
- Microsoft C# using XML and `HttpRequest`
- Java using libmonetra
- PHP using libmonetra
- Microsoft VB.Net using libmonetra
- Microsoft VBScript using XML and MSXML2
- Microsoft Visual Basic 6 using libmonetra

9 UniTerm Point of Interaction Devices

9.1. Supported POI Devices	28
9.1.1. Ingenico RBA information	29
9.1.2. Verifone VX XPI information	32
9.1.3. Ingenico CPX/uCPX information	32

Card data is captured at the point of sale via a magnetic swipe reader or, in some cases (such as for telephone-based transactions), by manual entry of the card number via a keyboard, touch screen, or key pad. The device where card data is captured is called the Point of Interaction (POI) device or also may be referred to as the "point of capture" or "point of entry" device.



Note: The UniTerm module supports both encrypting and non encrypting POI devices. Using the UniTerm module with non encrypting devices can remove the application software (such as a POS application) from scope for the PCI Payment Application (PA-DSS) standard. Using encrypting POI devices can also reduce or eliminate PCI requirements for merchants.

9.1 Supported POI Devices

The table below describes POI devices currently supported. The column marked ENCRYPTION indicates the type of encryption the device supports (if any). CardShield encryption can be performed by a Monetra server while other types of encryption must be preformed by the transaction processor. The column marked EMV are devices that UniTerm can work with to perform EMV/Chip based transactions.



Note: UniTerm is currently only supporting devices which support EMV. This list may be expanded in the future to support non-EMV devices. This list also does not include keyboard-emulation devices (both encrypting and non-encrypting) which are supported when running in GUI mode.

If you are using a previous version of Uniterm which supported additional non-EMV devices, do not upgrade your version of Uniterm as those devices are not currently supported.

Model	Device S/W	u_devicetype	Notes	Encryption	EMV
Ingenico					
iPP320 CPX	CPX	ingenico_cpx	Canada	NONE	x
iUP250 uCPX	uCPX	ingenico_ucpx	Canada	NONE	x
Ingenico RBA family (iPP320, iSC Touch 250, etc)	RBA	ingenico_rba	USA	CardShield, First Data TransArmor RSA	x
Verifone					
vx805	XPI	verifone_vx	USA	NONE	x

9.1.1 Ingenico RBA information

The minimum version of the RBA software load supported is v14 for running EMV transactions. The current recommended version is 15.06. Any device in the Ingenico RBA family may be used.

The RBA family includes all Ingenico Telium2 devices that can run the RBA (Retail Base Application) software. This includes, but is not limited to:

- iCMP
- iSMP companion
- iWL250
- iPP320 - PCI PTS v3.x version
- iPP350 - PCI PTS v3.x version
- iSC Touch 250
- iSC Touch 350
- iSC Touch 480

9.1.1.1 Communication Methods

UniTerm supports communicating with RBA via these communication methods (given the proper cables and add-on options from Ingenico):

- USB-HID - No drivers are necessary, select USB as the device connectivity in UniTerm
- USB<>Serial Conv - Requires Telium or Jungo drivers on Windows, will show up as a virtual COM port and be used as a Serial device in UniTerm (except for Linux where it may be used as a USB device).
- Serial - Settings: 115200 8N1 - No flow control
- Bluetooth - Android native, on Windows it should show up as a virtual COM port and be usable as a Serial device in UniTerm.
- Ethernet - Settings: IP server mode



Note: Not all devices support BlueTooth or USB-HID even if the menu lists it as an available option.

9.1.1.2 Device configuration

RBA devices can be configured by entering the management menu during device boot in order to set up the communication method. When a device is shipped to you, it can often be left in a state which is not compatible with the cabling being used and must be reconfigured. Please ensure you only select one of the supported communication methods as documented in the previous section.

In order to reboot a device, you may either disconnect it from power, or use the reboot key sequence. The key sequence is either the yellow CLEAR button plus the "* . , #" key or the "-" key, depending on which device is being used.

While booting, wait until the RBA splash screen appears with the scroll bars and system information. Then quickly press the management password, which by default is 2 6 3 4 and then the green ENTER key. Follow the on-screen prompts.

The communication method configuration is available via TDA -> Configuration -> Communication.

9.1.1.2.1 Contactless Support

Some devices such as the iPP320 have contactless as an optional module. It is possible when such a device is shipped to you, the optional module is installed but not activated. If you are certain the device has the necessary hardware for contactless, but contactless is not working, you may need to activate it. For the iPP320 this can be confirmed by observing the existence of a contactless chip behind the rear door of the device. Contactless must not be enabled if the device does not have the proper hardware.

In order to enable contactless, use the key sequence documented in the prior section to enter management mode. Then navigate to Telium manager -> Initialization -> Parameters -> Contactless and make sure it is set to Yes -> Internal.

9.1.1.3 Hardware Information

It is important to ensure the device being ordered is the latest hardware revision. Ingenico often introduces newer revisions without changing the model number, however their Part Numbers do in fact differ. The easiest way to request the most recent revision is to ensure you are requesting the PCI PTS v3 or v4 version of the devices. Older hardware revisions comply with PCI PTS v2 and should not be used for new deployments as you may experience issues due to limitations in the hardware.



Note: There have been recent reports of customers receiving iPP320 units that have been sent out as PCI PTS v2 devices. These devices do NOT support RBA12 and higher, even though they may come with a later RBA release. The part number on the supported devices will start with 11, while the part number on unsupported devices will start with 01. If you experience lockups or unexpected behavior, please verify your device is a PCI PTS v3 or higher device.

9.1.1.4 Forms and Images

UniTerm depends on the stock forms and images that ship by default on terminals with RBA. In addition, UniTerm does require a few UniTerm-specific forms and images to be available on the device. These will be generated and uploaded automatically to the device if UniTerm can not find them.

UniTerm will check if it has all the necessary forms on the first transaction run by a device. It will then load any missing forms. When loading forms is required, a message is presented on the device and there is an additional delay until the upload is complete.

It is possible for integrators to fully customize the look and feel of the forms displayed on the device. Such integrators should contact Ingenico in order to obtain the necessary form building

tools, and information on how to upload custom forms and images onto the device. Integrators should also contact their device distributor to ask about services to pre-load any files prior to shipping devices to customers. The forms used and their requirements are listed below.

Forms and Images used by UniTerm:

- `UTAD.K3Z` - The form displayed when the device is idle, also known as the "ADs" screen. This form may be customized to present an image or a series of rotating images, but must not contain buttons. The default form loaded contains a single image, `UTAD.PNG`. It is recommended that the images created be specific to the device for best appearance even though the device will scale the image if too small or large.
- `UTCCOD.K3Z` - Form used for card entry / selection. The form loaded is the same as the default Ingenico `CCOD.K3Z` form, with the exception that the `cancelenabled='true'` attribute has been added to allow the cardholder to press the physical cancel button to exit the request payment screen. Integrators wishing to modify this screen need to comply with the capabilities of the stock form.
- `UTCSEL.K3Z` - Form used for tender selection (credit, debit, etc). The form loaded is identical to the default Ingenico `PAY1.K3Z` form. It is duplicated due to an Ingenico limitation that does not allow the use of the stock form when using the "on demand" command mode. Integrators wishing to modify this form must comply with the capabilities of the stock form, especially the mapping of the button names available (e.g. `Bbtna` - debit, `Bbtnb` - credit, etc).
- `MSG.K3Z` - Form used to display single line messages. This is a stock form, any replacements should adhere to the capabilities of the stock form.
- `MSGTHICK.K3Z` - Form used to display double line messages. This is a stock form, any replacements should adhere to the capabilities of the stock form.
- `AMTV.K3Z` - Form used to display confirmation prompts, both for arbitrary prompts and amount confirmation. This is a stock form, any replacements should adhere to the capabilities of the stock form.
- Ingenico may internally call additional forms during the EMV payment processing flow. For information on how to customize these screens, integrators should contact Ingenico.

9.1.1.5 First Data TransArmor RSA Encryption

The Ingenico devices support First Data's TransArmor RSA encryption. TransArmor is First Data's P2PE encryption solution along with tokenization which must be enabled on the account both within First Data's systems as well as within Monetra. When configuring a Monetra account for TransArmor encryption, set the `Encryption` merchant configuration value to `IngenicoRSA`.

As part of the device loading procedure, a key request will be made to Monetra which will request the current key to use from First Data's systems. Monetra will then send that key identifier to `takeys.monetra.com:443` to look for an available signed package to load onto

the Ingenico device. Due to limitations in the Ingenico TransArmor implementation it is not possible to directly load the key from First Data's systems into the device. If the requested key package is not yet available, the existing key will be continued to be used until which time the updated package is made available.

TransArmor keys typically expire after 2 years, and new keys will be provided 90 days prior to expiration. All terminals on a given merchant account will share the same RSA public key.

9.1.2 Verifone vx XPI information

The minimum version of the XPI software load supported is v8.23a for running EMV transactions. Prior versions of XPI may work for non-EMV transactions, however this functionality has not been extensively tested. The recommended version is v8.24D.

9.1.2.1 Communication Methods

UniTerm supports communicating with the Verifone vx via these communication methods (given the proper cables and add-on options from Verifone):

- USB - Requires Vx USB Drivers available from www.verifone.com on Windows, will show up as a virtual COM port and be used as a Serial device in UniTerm (except for Linux where it may be used as a USB device).
- Serial (COM1) - 9600

When a device is shipped to you, it can often be left in a state which is not compatible with the cabling being used and must be reconfigured.

9.1.2.2 Device configuration

During device boot-up, it is possible to change the connectivity setting to match the cabling. When the XPI version is displayed during startup, press the alpha and 8 buttons simultaneously. You can then change the connectivity method by pressing the appropriate F<n> key.

9.1.3 Ingenico CPX/uCPX information

Ingenico CPX (attended) and uCPX (unattended) software loads are supported for Canadian merchants. These loads support both contact and contactless EMV processing for multiple card brands including Interac debit cards. The required software versions are 10.14 for CPX and 02.02 for uCPX.



Note: The MasterCard PayPass v2.1 kernel must be loaded into the device if supporting contactless MasterCard EMV. If the device is loaded with the PayPass v3.0 kernel, it will fail to accept PayPass transactions. Due to limitations in the Ingenico software, it is impossible for UniTerm to detect the version of the PayPass kernel in use, and the CPX and uCPX software versions are not tied to any PayPass kernel version.

9.1.3.1 Communication Methods

Uniterm supports communicating with CPX/uCPX via these communication methods (given the proper cables and add-on options from Ingenico):

- USB->Serial - Requires Telium or Jungo drivers on Windows, will show up as a virtual COM port.
- Serial - 9600 7bits Even Parity - No flow control
- IP/Ethernet - Even Parity



Note: Please contact Ingenico for assistance with configuring your device for proper communication. It is known that the on-screen menu system does NOT work when configuring Ethernet mode due to the inability to set the Parity to Even. The parity configuration is a crucial step in ensuring Ethernet connectivity is functional.

10 Certifications and Device Configurations

10.1. Certification List	34
10.2. Configuration Definitions	35

10.1 Certification List

EMV Certifications are tied to specific device versions, device configurations, and software versions. During deployment, it is crucial that only certified configurations are used.

Device configurations are based on the EMV kernel version in the device. The available configurations are listed as part of the EMV LOA (Letter of Approval) for the Level 2 kernel for the device. The approval letters can be obtained from EMVCO: <http://www.emvco.com/approvals.aspx?id=85>

Device	EMVKern/Conf	UniTerm	Module Version	Config
Chase Paymentech				
Ingenico iPP320 CPX	4.66/3C	8.0	Paymentech Tampa 3.2.0 (Jan 2015)	Canada, Attended, OfflinePin, Sig
Verifone vx805	6.2.0/1C	8.0	Paymentech Tampa 3.2.0 (Oct 2015)	USA, Attended, OnlinePin, OfflinePin, Sig
Moneris				
Ingenico iPP320 CPX	4.66/3C	8.0	Moneris SPDH 2.0.0 (Sep 2015)	Canada, Attended, OfflinePin, Sig
Ingenico iUN uCPX	4.66/15C	8.0	Moneris SPDH 2.0.0 (Sep 2015)	Canada, Unattended, OfflinePin, NoSig
First Data				
Ingenico RBA family	4.67/1C	8.0	First Data Cardnet or Nashville EDC 4.1.0 (Oct 2015)	USA, Attended, OnlinePin, OfflinePin, Sig
Verifone vx805	6.2.0/1C	8.0	First Data Cardnet or Nashville EDC 4.1.0	USA, Attended, OnlinePin, OfflinePin, Sig

Certifications and Device Configurations

Device	EMVKern/Conf	UniTerm	Module Version	Config
			(Nov 2015)	
Tsys				
Ingenico RBA family	4.67/1C	8.0	TSYS (aka Vital/VisaNet) 3.0.0 (Nov 2015)	USA, Attended, OnlinePin, OfflinePin, Sig
Verifone vx805	6.2.0/1C	8.0	TSYS (aka Vital/VisaNet) 3.0.0 (Nov 2015)	USA, Attended, OnlinePin, OfflinePin, Sig
Global Payments				
Ingenico RBA family	4.67/1C	8.0	Global Payments East 3.0.0 (Oct 2015)	USA, Attended, OnlinePin, OfflinePin, Sig
Verifone vx805	6.2.0/1C	8.0	Global Payments East 3.0.0 (Oct 2015)	USA, Attended, OnlinePin, OfflinePin, Sig
WorldPay				
Ingenico RBA family	4.67/1C	8.0	RBS WorldPay TCMP 2.0.0 (Oct 2015)	USA, Attended, OnlinePin, OfflinePin, Sig
Vantiv				
Ingenico RBA family	4.67/1C	8.0	Vantiv/FifthThird 610 2.1.0 (Dec 2015)	USA, Attended, OnlinePin, OfflinePin, Sig


10.2 Configuration Definitions

EMV configurations are strictly certified in an "all or nothing" manner. You must choose an explicit certification from the list in the prior section and all configuration parameters must be adhered to. For instance, if the certification lists both OnlinePin and OfflinePin, you cannot simply choose to support only OfflinePin.

The meanings of the various configurations listed in the prior section are below:

Key	Description
USA	Certified for use in the United States
Canada	Certified for use in Canada

Certifications and
Device Configurations

Key	Description
Attended	The environment is monitored by a clerk such as Retail, Restaurant, or Lodging. Not usable in a Kiosk environment such as a parking meter or gas pump.
Unattended	The environment is NOT monitored by a clerk, for use in kiosk type environments.
OnlinePin	<p>An encrypted PIN can be obtained from a cardholder and sent to the processor with the transaction. When supporting Online PIN it is required that the device be injected with a 3DES DUKPT PIN key specific to the processing institution in use prior to deployment by a merchant.</p> <div>  <p>Note: OnlinePin may not be supported for all card brands of a given processing institution. UniTerm will automatically adjust support for the processor's card brand limitations where necessary.</p> </div>
OfflinePin	The terminal will negotiate the PIN directly with the chip embedded into the card without the need to send the PIN to the processing institution. A terminal does not need a Pin Debit key injected into it if only OfflinePin (and not OnlinePin) is supported.
Sig	Signature cardholder verification is supported. This may either be a signature capture capable device or a signature obtained via paper receipt.

A UniTerm Device Loading

When loading a device with Uniterm, Uniterm will send Monetra a list of terminal configurations from the Letter of Approval (LOA) as provided by device manufacturer for the device's EMV kernel. Monetra will compare this list to merchant defined settings. Monetra will then select a usable LOA configuration and return to Uniterm loading data which has been merged with the merchant's settings.

Some terminal loading data is mandatory and cannot deviate from a LOA configuration. Other data is merchant configurable and is allowed to be changed. Data that is configurable will be merged into an LOA configuration by Monetra based on the merchant's settings.

In the event no LOA configuration is valid for the merchant's settings then Monetra will respond with an error. Also, If the device's EMV kernel version is not certified for use with Uniterm loading will result in an error.

After a successful load the integration must check `altered_termload`. If it is "yes" then not all of the merchant's settings could be used and some of the values have been ignored. The integration can compare the selected values with the `*_desired` and `*_loa` values to determine what was ignored. It is the choice of the integration to either accept the load with the selected values or return an error if the merchant's setting have been altered due to being unsupported by the devices LOA configurations.



Note: If using implicit/auto device loading and not calling `u_action=device_load` directly, an integrator will have no ability to retrieve the `device_load` parameters.

PARAMETER	OVERVIEW
<code>altered_termload</code>	If no LOA configuration matches the merchant's settings a valid LOA will be used and the merchant's settings will be overridden. This indicates this has happened.
<code>termtype_desired</code>	The terminal type Monetra has determined fits the merchant's settings.
<code>termcaps_desired</code>	Terminal capabilities configured in Monetra. These are features that the merchant has selected for use.
<code>addltermcaps_desired</code>	Additional terminal capabilities configured in Monetra. These are features that the merchant has selected for use.
<code>termcaps_loa</code>	Terminal capabilities from the LOA configuration Monetra has selected.
<code>addltermcaps_loa</code>	Additional terminal capabilities from the LOA configuration Monetra has selected.
<code>loa_id</code>	The LOA configuration id Monetra has selected for use. This is the id in the device certification document for the kernel version located at: http://www.emvco.com/approvals.aspx?id=85
<code>termtype</code>	The terminal type from the LOA configuration that will be loaded into the device.

termcaps	Terminal capabilities from the merged LOA configuration and merchant's settings that will be loaded into the device. Note: mandatory LOA configuration data will not be changed.
addltermcaps	Additional terminal capabilities from the merged LOA configuration and merchant's settings that will be loaded into the device. Note: mandatory LOA configuration data will not be changed.

Example device load response:

```
u_errorcode = SUCCESS
code = AUTH
verbiage = Device loaded
altered_termload = no
termtype_desired = 21
termcaps_desired = E0B8C8
addltermcaps_desired = 6000F0F001
termcaps_loa = 60B8C8
addltermcaps_loa = 6000F0A001
loa_id = 18C
termtype = 22
termcaps = E0B8C8
addltermcaps = 6000F0F001
```

B EMV Receipt Requirements

The UniTerm application never generate receipts. It is the integrator's responsibility to generate all proper receipts for both customer and merchant retention. What constitutes a proper receipt is dependent on a number of factors such as industry, card present vs card not present, and card entry method (for card present).

The purpose of this section is to provide general information about the receipt data UniTerm will return and how to use it generate a receipt. This does not cover all aspects of receipt generation. It also does not cover processor specific formatting requirements. It is recommended to verify receipts and receipt formatting with your processor before going into production.

Also there are typically two types of receipts printed. A merchant and a customer copy. Each one will have most of the same information but there are slight differences between the two.

B.1 Receipt content

B.1.1 Base receipt content

Receipts should include the following blocks and data elements in roughly the order provided below. All data is required if returned by UniTerm, or otherwise available, unless otherwise noted.

- Merchant Info Header
 - Name - `merch_name`
 - Address - `merch_addr1`, `merch_addr2`, `merch_addr3`
 - Phone (optional) - `merch_phone`
 - Email (optional) - `merch_email`
 - Website (optional) - `merch_url`
 - Merchant ID - required by some processors. Recommended to omit or truncate, see `merch_id` response documentation for more information.
 - Lane ID (optional) - `laneid` or `stationid` request parameter.
- Transaction type - request parameter `action` or equivalent text
- Card information
 - Type - `cardtype`
 - Entry mode - `rcpt_entry_mode` - or equivalent text, some processors may have explicit mappings they require.
 - Interac Account Type - `rcpt_acct_type` or for Interac Flash (contactless) transactions, must display `INTERAC FLASH DEFAULT`. Integrators must convert the UniTerm-returned value of `checking` to `chequing` to comply with Interac requirements.
 - Masked Account Number - `account`
- Transaction reference info
 - Date and time - `rcpt_host_ts` or `timestamp`
 - Identifier - request parameters `ordernum` or `ptransnum`
 - Additional identifiers (optional) - request parameters such as `custref`
 - `ttid` (optional) - either request or response `ttid`
 - Batch number - `batch`

- Auth number (if authorized) - `auth`
- Trace information - `stan`
- Processor response code (some processors may require this) - `rcpt_resp_code`
- Issuer response code (some processors may require this) - `rcpt_issuer_resp_code`
- Processor specific custom data - see `rcpt_custom`
- Monetary amounts
 - Tip - Request parameter `examount`
 - Tax - Request parameter `tax`
 - Cash back - Request parameter `cashbackamount`
 - Authorized Amount - `authamount` if returned, otherwise request parameter `amount`
 - Balance - `balance`
- Transaction disposition
 - Card disposition - See Card Disposition documentation
 - Partial Approval Indicator - if `authamount` returned
 - Overall disposition (approved/declined) - `code`
- Additional Print Data - `printdata`, Additional data meant to be printed on the receipt as provided by the processor. Often used for gift/loyalty programs.
- Cardholder Verification
 - Signature line (if necessary) - `u_need_signature=yes`
 - Cardholder Name, centered under signature line if a signature line is shown (optional) - `cardholdername`
- EMV data
 - Application name - `rcpt_emv_name`
 - AID - `rcpt_emv_aid`
 - TVR - `rcpt_emv_tvr`
 - TSI - `rcpt_emv_tsi`
 - Application Cryptogram Type and Cryptogram Value (optional) - `rcpt_emv_actype` and `rcpt_emv_ac`
- Cardholder Notice (such as stating merchant vs customer copy) (optional) - see receipt examples

B.2 Receipt Data Returned by UniTerm

PARAMETER	OVERVIEW
<code>timestamp</code>	Unix timestamp representing the time and date the transaction took place, this should be used to derive the transaction date if <code>rcpt_host_ts</code> is not returned.
<code>rcpt_host_ts</code>	(REQUIRED): The time and date recorded from the processor the transaction took place. MMDDYYHHMMSS format. Use <code>timestamp</code> if this value is not present in the response.
<code>rcpt_entry_mode</code>	(REQUIRED): Indicates how the card data was captured. Possible values are: <ul style="list-style-type: none"> • G: Keyed entry (EMV Fallback) • M: Keyed entry • T: EMV Contactless

EMV Receipt Requirements

	<ul style="list-style-type: none"> • C: EMV Contact • F: Swipe (EMV Fallback) • R: MSD (RFID) Contactless • S: Swipe • I: MICR Check Read
rcpt_acct_type	Interac specific account type chosen by the customer.
rcpt_emv_cvm	<p>For EMV transactions this is the cardholder verification method performed. Possible values are:</p> <ul style="list-style-type: none"> • none • sig • pin • pinsig • unknown <p>For "pin" and "pinsig" the receipt should say "VERIFIED BY PIN". For "sig" a signature should be captured.</p>
rcpt_resp_code	Response code returned from the processing institution.
rcpt_issuer_resp_code	Response code returned from the issuer.
language	Cardholder's language preference. The receipt should be created using this language if possible and shall contain the 2 character ISO language code.
batch	The batch number associated with the transaction.
cardtype	Monetra cardtype value. This is the value that would have been configured in supported card types for the account. Use this to take card specific action in receipt generation.
balance	Current balance on the card after the transaction.
rcpt_emv_aid	Card Application ID (AID) used
rcpt_emv_name	Textual name of card application used.
rcpt_emv_tvr	Transaction verification results.
rcpt_emv_tsi	Transaction status information.
rcpt_emv_actype	<p>(optional). Application Cryptogram type.</p> <ul style="list-style-type: none"> • AAC - Application Authentication Cryptogram (decline) • ARQC - Application Request Cryptogram (intermediate or contactless)

	<ul style="list-style-type: none"> TC - Transaction Certificate (offline or final approval)
rcpt_emv_ac	(optional). Application Cryptogram.
code	Used to determine if the transaction was approved or declined.
account	Masked account number.
cardholdername	Customers name as encoded on the card.
auth	Authorization code.
stan	Processor system trace information (mainly used for pin-debit transactions).
authamount	If the amount authorized is different than the requested amount this is the amount that must show on the receipt. It is possible that the integration could pool multiple transactions on one receipt and in that case the authamount needs to be present for each card along with other card specific receipt data. Note that some processors do not allow pooling card data onto one receipt and require separate receipts per card.
rcpt_custom	List of comma separated key:value pairs with additional processor specific data that needs to appear on the receipt.
u_errorcode	On failure this will provide some information about the failure. Specifically important to receipt processing are the EMV_CARD_REMOVED and EMV_CARD_DENY values.
u_need_signature	Used to determine if a signature line is required.
printdata	Additional processor-provided data returned by some processors that is intended to be printed on receipts. Often used for Gift/Loyalty programs. Please consult with your processor for more information.
issuer_decline	Boolean (yes/no). Currently this value is only returned by Moneris, and is used to indicate if a decline was due to an issuer decline or a local processor decline. The purpose of this response parameter is that Moneris has different receipt messaging requirements based on who declined the transaction.
merch_name	Merchant Name if configured in merchant profile. Cached by UniTerm from merchainfo request and sent on every transaction response.

merch_addr1	Merchant Address Line 1 if configured in merchant profile. Cached by UniTerm from <code>merchinfo</code> request and sent on every transaction response.
merch_addr2	Merchant Address Line 2 if configured in merchant profile. Cached by UniTerm from <code>merchinfo</code> request and sent on every transaction response.
merch_addr3	Merchant Address Line 3 if configured in merchant profile. Cached by UniTerm from <code>merchinfo</code> request and sent on every transaction response.
merch_phone	Merchant Phone Number if configured in merchant profile. Cached by UniTerm from <code>merchinfo</code> request and sent on every transaction response.
merch_email	Merchant Contact Email if configured in merchant profile. Cached by UniTerm from <code>merchinfo</code> request and sent on every transaction response.
merch_url	Merchant URL or Website if configured in merchant profile. Cached by UniTerm from <code>merchinfo</code> request and sent on every transaction response.
merch_id	Merchant ID truncated to only the last 4 digits if available. Cached by UniTerm from <code>merchinfo</code> request and sent on every transaction response. The Merchant ID is required by some processors for EMV, though due to rampant "return fraud", we strongly discourage integrators from providing the full Merchant ID on receipts. Instead, if you choose to display the merchant id, it should display only the last 4 digits. This field can be used for that purpose.
merch_proc	Merchant Processing Institution (internal name) used. Cached by UniTerm from <code>merchinfo</code> request and sent on every transaction response. This may be used to trigger different receipt formats based on processor-specific requirements.

B.3 Receipt Data NOT Returned by UniTerm

This information is data that may have been sent to UniTerm on the request that should be on the receipt.

PARAMETER	OVERVIEW
Transaction Type	The initiating application should know which transaction type is being performed (Sale, Refund etc.).
Transaction Identifier	ordernum or ptrannum if present.
Additional Identifier	custref if present.
ttid	When performing a transaction such as return by ttid the referenced ttid should be present on the receipt. This will aid in tracking the original transaction that was returned.
Amount Information	<ul style="list-style-type: none"> • Tip - Tip amount for order as provided in the examount field in request. • Tax - Tax amount for order • Amount - Authorized amount, either the amount passed in or the partially approved amount provided in the authamount field. • Cash Back Amount - Amount of Cash Back (currently not supported)
Card Disposition	<ul style="list-style-type: none"> • When u_errorcode is EMV_CARD_REMOVED, should say: "CARD REMOVED" • When u_errorcode is EMV_CARD_DENY, should say: "DECLINED BY CARD" • When rcpt_emv_cvm is pin or pinsig, should say: "VERIFIED BY PIN" • When rcpt_entry_mode is F or G, should say: "CHIP CARD SWIPED" • When authamount is returned and is not equal to requested amount, should say: "TRANSACTION PARTIALLY APPROVED" • When code is CALL, should say: "CALL ISSUER"

B.4 Signature Line Requirements

The only time a signature line is necessary when using Uniterm is when u_need_signature=yes. Internally Uniterm will handle logic to determine if the signature line is needed on the paper receipt.

When set to yes this indicates that a signature line is required on the receipt. If possible Uniterm will attempt to capture the signature through the device. If this fails or is not possible then this value will indicate that signature is still required.

B.5 Merchant vs Customer Copy

For the most part merchant and customer receipt requirements are identical, though there are a couple of minor exceptions.

Merchant receipts must NOT contain a balance line

Customer receipt must not contain a signature line

B.6 Moneris Requirements

Moneris has additional receipt requirements that are not covered by this section due to direct contradictions with requirements as provided by other processing institutions and the card brands themselves. The receipt requirements documented are insufficient to comply with Moneris requirements but do comply with the card brand requirements. The additional requirements imposed are specific to Moneris and appear to be arbitrary, a large enough merchant might be able to negotiate different receipt formats since there is no industry regulation being followed.

If intending to work with Moneris, it is required that integrators create a custom receipt template specific to Moneris that is used only on Moneris, and a separate template that is used for all other processors. Integrators must contact Moneris directly to receive their receipt formatting requirements. UniTerm does return sufficient data to format the Moneris-specific receipts, it simply may require some data to be manipulated, formatted, or translated to different languages to comply with their requirements.

B.7 Receipt Examples

Main Street successfully certified EMV, across several processors, using the examples provided below. Note these examples were designed to format properly on a common 25 character receipt printer.



Note: Receipt requirements required for the card brands for EMV and various processors tend to be very strict. We strongly recommend integrators make their receipts resemble those of the examples as closely as possible. Any divergence from the receipt examples provided below may require you seek validation of such receipts from your processor.

B.7.1 EMV Insert, Signature Required

B.7.1.1 Uniterm Response Data

PARAMETER	VALUE
account	XXXXXXXXXXXX0119
auth	152013
batch	1
cardholdername	VISA ACQUIRER TEST/CARD 01
cardlevel	VISA_TRADITIONAL
cardtype	VISA
code	AUTH
item	27

EMV Receipt Requirements

language	en
merch_addr1	123 STREET NAME
merch_addr2	CITY, STATE ZIP
merch_id	1834
merch_name	MERCHANT NAME
merch_phone	(888) 555-1234
merch_proc	GLOBALPAY
msoft_code	INT_SUCCESS
pclevel	0
phard_code	SUCCESS
rcpt_custom	REC #:000027,TRN REF #:355724280069888,VAL CODE:BBCD
rcpt_emv_ac	8F73ED36C8F2C099
rcpt_emv_actype	TC
rcpt_emv_aid	A0000000031010
rcpt_emv_cvm	sig
rcpt_emv_name	CREDITO DE VISA
rcpt_emv_tsi	F800
rcpt_emv_tvr	0280008000
rcpt_entry_mode	C
rcpt_host_ts	092215174640
rcpt_issuer_resp_code	00
rcpt_resp_code	000
stan	378222
timestamp	1442944083
ttid	29
u_errorcode	SUCCESS
u_need_signature	yes
verbiage	AP

B.7.1.2 Example Receipt

MERCHANT NAME 123 STREET NAME CITY, STATE ZIP (888) 555-1234 SALE	
MID: 1834	Lane: 1
VISA	C

EMV Receipt Requirements

Card: XXXXXXXXXXXX0119
Time: 09/22/15 17:46:40
Order #: 1842
TTID: 29
RespCode: 00/000
Auth: 152013 Batch: 1
STAN: 378222
REC #: 000027
TRN REF #: 355724280069888
VAL CODE: BCD

AMOUNT: 1.00

APPROVED

SIGNATURE

X

VISA ACQUIRER TEST/CARD
01

CARDHOLDER WILL PAY CARD
ISSUER ABOVE AMOUNT
PURSUANT TO CARDHOLDER
AGREEMENT

CREDITO DE VISA
AID A0000000031010
TVR 0280008000
TSI F800
TC 8F73ED36C8F2C099

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

MERCHANT COPY

MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 1834 Lane: 1
VISA C
Card: XXXXXXXXXXXX0119
Time: 09/22/15 17:46:40
Order #: 1842
TTID: 29
RespCode: 00/000
Auth: 152013 Batch: 1
STAN: 378222
REC #: 000027
TRN REF #: 355724280069888
VAL CODE: BCD

AMOUNT: 1.00

APPROVED

CREDITO DE VISA

EMV Receipt Requirements

AID A0000000031010
TVR 0280008000
TSI F800
TC 8F73ED36C8F2C099

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

CUSTOMER COPY

B.7.2 EMV Insert, PIN Verified**B.7.2.1 Uniterm Response Data**

PARAMETER	VALUE
account	XXXXXXXXXXXX0036
auth	602664
batch	1
cardholdername	VISA ACQUIRER TEST/CARD 03
cardlevel	VISA_TRADITIONAL
cardtype	VISA
code	AUTH
item	7
language	en
merch_addr1	123 STREET NAME
merch_addr2	CITY, STATE ZIP
merch_id	1834
merch_name	MERCHANT NAME
merch_phone	(888) 555-1234
merch_proc	GLOBALPAY
msoft_code	INT_SUCCESS
pclevel	0
phard_code	SUCCESS
rcpt_custom	REC #:000007,TRN REF #:638114437174992,VAL CODE:BBCD
rcpt_emv_ac	2F0346EBCA494BF4
rcpt_emv_actype	TC
rcpt_emv_aid	A0000000031010
rcpt_emv_cvm	pin
rcpt_emv_name	CREDITO DE VISA
rcpt_emv_tsi	F800
rcpt_emv_tvr	0080008000
rcpt_entry_mode	C
rcpt_host_ts	092215172258
rcpt_issuer_resp_code	00
rcpt_resp_code	000
stan	563536

EMV Receipt Requirements

timestamp	1442942662
ttid	7
u_errorcode	SUCCESS
verbiage	AP

B.7.2.2 Example Receipt

```
MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 1834          Lane: 1
VISA                C
Card:  XXXXXXXXXXXX0036
Time:  09/22/15 17:22:58
Order #:           5705
TTID:              7
RespCode:          00/000
Auth: 602664      Batch: 1
STAN:              563536
REC #:             000007
TRN REF #:638114437174992
VAL CODE:          BBCD

AMOUNT:            337.00

VERIFIED BY PIN

APPROVED

CREDITO DE VISA
AID A0000000031010
TVR 0080008000
TSI F800
TC 2F0346EBCA494BF4

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

MERCHANT COPY

-----

MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 1834          Lane: 1
VISA                C
Card:  XXXXXXXXXXXX0036
Time:  09/22/15 17:22:58
Order #:           5705
TTID:              7
RespCode:          00/000
```

EMV Receipt Requirements

Auth: 602664 Batch: 1
STAN: 563536
REC #: 000007
TRN REF #:638114437174992
VAL CODE: BCD

AMOUNT: 337.00

VERIFIED BY PIN

APPROVED

CREDITO DE VISA
AID A0000000031010
TVR 0080008000
TSI F800
TC 2F0346EBCA494BF4

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

CUSTOMER COPY

B.7.3 EMV Insert, No CVM**B.7.3.1 Uniterm Response Data**

PARAMETER	VALUE
account	XXXXXXXXXXXX1005
auth	232508
batch	1
cardholdername	AEIPS 32/VER 1.0
cardtype	AMEX
code	AUTH
item	2
language	en
merch_addr1	123 STREET NAME
merch_addr2	CITY, STATE ZIP
merch_id	1836
merch_name	MERCHANT NAME
merch_phone	(888) 555-1234
merch_proc	GLOBALPAY
msoft_code	INT_SUCCESS
pclevel	0
phard_code	SUCCESS
rcpt_custom	REC #:000002,TRN REF #:416237190201752
rcpt_emv_ac	5C221DC28EB72FCF
rcpt_emv_actype	TC
rcpt_emv_aid	A000000025010801
rcpt_emv_cvm	none
rcpt_emv_name	AMERICAN EXPRESS
rcpt_emv_tsi	F800
rcpt_emv_tvr	0000008000
rcpt_entry_mode	C
rcpt_host_ts	092515194045
rcpt_issuer_resp_code	000
rcpt_resp_code	000
stan	000514
timestamp	1443210133

EMV Receipt Requirements

ttid	79
u_errorcode	SUCCESS
verbiage	AP

B.7.3.2 Example Receipt

```
MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 1836          Lane: 1
AMEX                C
Card:              XXXXXXXXXXXX1005
Time: 09/25/15 19:40:45
Order #:           41
TTID:              79
RespCode:          000/000
Auth: 232508       Batch: 1
STAN:              000514
REC #:             000002
TRN REF #:416237190201752

AMOUNT:            62.00

APPROVED

AMERICAN EXPRESS
AID A000000025010801
TVR 0000008000
TSI F800
TC 5C221DC28EB72FCF

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

MERCHANT COPY

-----

MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 1836          Lane: 1
AMEX                C
Card:              XXXXXXXXXXXX1005
Time: 09/25/15 19:40:45
Order #:           41
TTID:              79
RespCode:          000/000
Auth: 232508       Batch: 1
STAN:              000514
REC #:             000002
TRN REF #:416237190201752
```

EMV Receipt Requirements

AMOUNT: 62.00

APPROVED

AMERICAN EXPRESS
AID A000000025010801
TVR 0000008000
TSI F800
TC 5C221DC28EB72FCF

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

CUSTOMER COPY

B.7.4 EMV Insert, Card Decline**B.7.4.1 Uniterm Response Data**

PARAMETER	VALUE
account	XXXXXXXXXXXX0010
cardtype	VISA
code	DENY
merch_addr1	123 STREET NAME
merch_addr2	CITY, STATE ZIP
merch_id	1834
merch_name	MERCHANT NAME
merch_phone	(888) 555-1234
merch_proc	GLOBALPAY
rcpt_emv_ac	BA9BD3FAC8ADD6C7
rcpt_emv_actype	AAC
rcpt_emv_aid	A0000000031010
rcpt_emv_cvm	pin
rcpt_emv_name	CREDITO DE VISA
rcpt_emv_tsi	E800
rcpt_emv_tvr	0280A08000
rcpt_entry_mode	C
rcpt_host_ts	092215134154
u_errorcode	EMV_CARD_DENY
verbiage	Transaction aborted - declined by card

B.7.4.2 Example Receipt

```

MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 1834           Lane: 1
VISA                C
Card:  XXXXXXXXXXXX0010
Time:  09/22/15 13:41:54
Order #:             17421

AMOUNT:             22.00

```

DECLINED BY CARD VERIFIED BY PIN
DECLINED
CREDITO DE VISA AID A0000000031010 TVR 0280A08000 TSI E800 AAC BA9BD3FAC8ADD6C7
IMPORTANT - RETAIN THIS COPY FOR YOUR RECORDS
MERCHANT COPY

MERCHANT NAME 123 STREET NAME CITY, STATE ZIP (888) 555-1234
SALE
MID: 1834 Lane: 1 VISA C Card: XXXXXXXXXXXXX0010 Time: 09/22/15 13:41:54 Order #: 17421
AMOUNT: 22.00
DECLINED BY CARD VERIFIED BY PIN
DECLINED
CREDITO DE VISA AID A0000000031010 TVR 0280A08000 TSI E800 AAC BA9BD3FAC8ADD6C7
IMPORTANT - RETAIN THIS COPY FOR YOUR RECORDS
CUSTOMER COPY

B.7.5 EMV Insert, Card Removed (Decline)**B.7.5.1 Uniterm Response Data**

PARAMETER	VALUE
code	DENY
merch_addr1	123 STREET NAME
merch_addr2	CITY, STATE ZIP
merch_id	1818
merch_name	MERCHANT NAME
merch_phone	(888) 555-1234
merch_proc	GLOBALPAY
u_errorcode	EMV_CARD_REMOVED
verbiage	Card Removed

B.7.5.2 Example Receipt

```

MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 1818      Lane: 1
Time: 09/24/15 14:43:46
Order #:      6224

AMOUNT:      1.00

CARD REMOVED

DECLINED

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

MERCHANT COPY
-----

MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 1818      Lane: 1
Time: 09/24/15 14:43:46
Order #:      6224

```

EMV Receipt Requirements

AMOUNT: 1.00

CARD REMOVED

DECLINED

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

CUSTOMER COPY

B.7.6 EMV Insert, Interac

B.7.6.1 Uniterm Response Data

PARAMETER	VALUE
account	XXXXXXXXXXXX1933
auth	175180
avs	UNKNOWN
batch	1
cardholdername	Test Card 1
cardtype	INTERAC
code	AUTH
item	10
language	en
merch_addr1	123 STREET NAME
merch_addr2	CITY, STATE ZIP
merch_id	3636
merch_name	MERCHANT NAME
merch_phone	(888) 555-1234
merch_proc	PAYMENTECH
msoft_code	INT_SUCCESS
pclevel	0
phard_code	SUCCESS
rcpt_acct_type	checking
rcpt_emv_ac	882D8427A268E214
rcpt_emv_actype	TC
rcpt_emv_aid	A0000002771010
rcpt_emv_cvm	pin
rcpt_emv_name	Interac
rcpt_emv_tsi	7800
rcpt_emv_tvr	8000008000
rcpt_entry_mode	C
rcpt_host_ts	092515155118
rcpt_resp_code	A
stan	00298722
timestamp	1443210676

EMV Receipt Requirements

ttid	10
u_errorcode	SUCCESS
verbiage	APPROVED

B.7.6.2 Example Receipt

```

MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 3636          Lane: 1
INTERAC           C
Acct Type:        CHEQUING
Card:             XXXXXXXXXXXX1933
Time:             09/25/15 15:51:18
Order #:          899065992
TTID:             10
RespCode:         A
Auth: 175180      Batch: 1
STAN:             00298722

AMOUNT:           5.01

VERIFIED BY PIN

APPROVED

Interac
AID A00000002771010
TVR 8000008000
TSI 7800
TC 882D8427A268E214

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

MERCHANT COPY

-----

MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 3636          Lane: 1
INTERAC           C
Acct Type:        CHEQUING
Card:             XXXXXXXXXXXX1933
Time:             09/25/15 15:51:18
Order #:          899065992
TTID:             10
RespCode:         A
Auth: 175180      Batch: 1
STAN:             00298722

```


EMV Receipt Requirements

AMOUNT: 5.01

VERIFIED BY PIN

APPROVED

Interac

AID A00000002771010

TVR 8000008000

TSI 7800

TC 882D8427A268E214

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

CUSTOMER COPY

B.7.7 EMV Contactless, Interac Flash Decline**B.7.7.1 Uniterm Response Data**

PARAMETER	VALUE
account	XXXXXXXXXXXXXXXX1311
cardtype	INTERAC
code	DENY
issuer_decline	yes
language	en
merch_addr1	123 STREET NAME
merch_addr2	CITY, STATE ZIP
merch_id	1625
merch_name	MERCHANT NAME
merch_phone	(888) 555-1234
msoft_code	INT_SUCCESS
phard_code	GENERICFAIL
printdata	CARD CANCELLED*REFER TO BRANCH
rcpt_acct_type	flash
rcpt_custom	refnum:660136000010016710
rcpt_emv_ac	ED538D29D3390729
rcpt_emv_actype	ARQC
rcpt_emv_aid	A0000002771010
rcpt_emv_cvm	unknown
rcpt_emv_name	Interac
rcpt_emv_tvr	0080008000
rcpt_entry_mode	T
rcpt_host_ts	072015180303
rcpt_issuer_resp_code	05
rcpt_resp_code	058
sequenceid	671
timestamp	1437429783
ttid	861
u_errorcode	MONETRA_ERROR
verbiage	DECLINED * CARD CANCELLED

B.7.7.2 Example Receipt

```
MERCHANT NAME
123 STREET NAME
CITY, STATE ZIP
(888) 555-1234

SALE

MID: 1625           Lane: 1
INTERAC             T
Acct Type: FLASH DEFAULT
Card: XXXXXXXXXXXXXXX1311
Date/Time: 072015180303
Order #: 899065992
TTID: 861
refnum:660136000010016710

AMOUNT: 1.09

DECLINED

Interac
AID A0000002771010
TVR 0080008000
ARQC ED538D29D3390729

IMPORTANT - RETAIN THIS
COPY FOR YOUR RECORDS

MERCHANT/CUSTOMER COPY
```

B.7.8 EMV Contactless, Decline**B.7.8.1 Uniterm Response Data**

PARAMETER	VALUE
account	XXXXXXXXXXXX0010
cardholdername	ETEC/PAYPASS
cardtype	MC
code	DENY
language	en
merch_addr1	123 STREET NAME
merch_addr2	CITY, STATE ZIP
merch_id	1625
merch_name	MERCHANT NAME
merch_phone	(888) 555-1234
msoft_code	INT_SUCCESS
phard_code	GENERICFAIL
rcpt_custom	refnum:660136000010016700
rcpt_emv_ac	16D1284D85A29DF2
rcpt_emv_actype	ARQC
rcpt_emv_aid	A0000000041010
rcpt_emv_cvm	none
rcpt_emv_name	PPC MCD 01 v2 2
rcpt_emv_tvr	0000008000
rcpt_entry_mode	T
rcpt_issuer_resp_code	51
rcpt_resp_code	481
sequenceid	670
timestamp	1437429662
ttid	860
u_errorcode	MONETRA_ERROR
verbiage	DECLINED *

B.7.8.2 Example Receipt

MERCHANT NAME
 123 STREET NAME
 CITY, STATE ZIP
 (888) 555-1234

EMV Receipt Requirements

```

      SALE
MID: 1625          Lane: 1
MC                T
Card:  XXXXXXXXXXXX0010
Date/Time:  072015180102
Order #:      899065992
TTID:        860
refnum:660136000010016700

AMOUNT:          10.51

      DECLINED

PPC MCD 01 v2 2
AID A0000000041010
TVR 0000008000
ARQC 16D1284D85A29DF2

  IMPORTANT - RETAIN THIS
    COPY FOR YOUR RECORDS

  MERCHANT/CUSTOMER COPY
```

C UniTerm Code Examples

C.1 Microsoft C# using libmonetra

```
1  /* Monetra Uniterm example program in C#
2  *
3  * Depends on the libmonetra C# .Net native API
4  *
5  * Implemented based on the Monetra Uniterm Guide in conjunction with the
6  * Monetra Client Interface Protocol Specification
7  *
8  * Please contact support@monetra.com with any questions
9  */
10 using System;
11 using System.Collections;
12 using System.Diagnostics;
13 using System.IO;
14 using System.Text;
15 using System.Threading;
16 using libmonetra;
17
18 /* NOTE: if compiling with Mono, you can use
19 *      gmcs /unsafe utest.cs libmonetra.cs
20 */
21
22 class UTest {
23     /* Uniterm Connectivity Information
24     * NOTE: this is the default, it is possible to change, but 99%
25     *       of deployments will probably use this Uniterm information
26     *       as-is
27     */
28     private const string uniterm_host    = "localhost";
29     private const int    uniterm_port    = 8123;
30
31     /* Authentication information
32     * NOTE: This information corresponds with the public test server
33     *       at testbox.monetra.com:8665 */
34     private const string monetra_user    = "test_retail:public";
35     private const string monetra_pass    = "publ1ct3st";
36
37
38     static string uniterm_path()
39     {
40         switch (Environment.OSVersion.Platform) {
41             case PlatformID.Win32NT:
42             case PlatformID.Win32S:
43             case PlatformID.Win32Windows:
44             case PlatformID.WinCE:
45                 return "C:\\Program Files\\Main Street Softworks\\Monetra Uniterm\\monetra_uniterm.exe";
46             default:
47                 return "/usr/local/monetra/bin/monetra_uniterm";
48         }
49     }
50
51     /*! Function to launch the Uniterm from the current process.
```

```

52  * If we don't launch it from the current process, it won't be given
53  * focus! (at least on Windows this is true, until the first
54  * manual focus is performed by an end-user) */
55  static void uniterm_launch()
56  {
57      Process uniterm                = new Process();
58      uniterm.StartInfo.FileName      = uniterm_path();
59      uniterm.StartInfo.CreateNoWindow = true;
60
61      uniterm.Start();
62
63      /* Make sure Uniterm is ready before returning,
64       * Sleep 1000ms (1s) */
65      System.Threading.Thread.Sleep(1000);
66  }
67
68
69  /*! Function to connect to an endpoint which uses the standard 'monetra'
70   * style protocol (so either Monetra itself, or Uniterm)
71   * \param[in] host      Resolvable hostname or IP address to connect to
72   * \param[in] port      Port associated with hostname to establish an SSL
73   *                      connection to
74   * \param[out] errorstr Textual error message if returns null
75   * \return Initialized connection class on success. null on failure
76   */
77  static Monetra uniterm_connect_host(string host, int port, ref string errorstr)
78  {
79      /* Initialize the Class */
80      Monetra conn = new Monetra();
81
82      errorstr = "";
83
84      /* We always want to use an SSL connection to Monetra and Uniterm */
85      conn.SetSSL(host, port);
86
87      /* Do not verify the SSL certificate, Monetra and the Uniterm
88       * use self-signed certificates by default which cannot be validated.
89       * The connection is still encrypted, the endpoint just isn't strictly
90       * validated */
91      conn.VerifySSLCert(false);
92
93      /* This makes it so TransSend() will block until a response is
94       * received from Monetra. Simplifies the API since we will never
95       * have more than one outstanding transaction per connection in
96       * this application */
97      conn.SetBlocking(true);
98
99      /* Connect! */
100     if (!conn.Connect()) {
101         errorstr = conn.ConnectionError();
102         return null;
103     }
104
105     return conn;
106 }
107
108
109 /*! Wrapper function to connect to Uniterm

```

```

110  * \param[out] errorstr Textual error message if returns null
111  * \return Initialized connection class on success. null on failure
112  */
113  static Monetra uniterm_connect(ref string errorstr)
114  {
115      Monetra conn;
116      string myerror = "";
117      conn = uniterm_connect_host(uniterm_host, uniterm_port, ref myerror);
118      if (conn == null) {
119          errorstr = "Connection to Uniterm Failed: " + myerror;
120      }
121      return conn;
122  }
123
124
125  /*! Request a transaction from Uniterm as documented in the Uniterm Guide.
126  * The Key/Value pair params are a combination of the Parameters as
127  * documented in the Uniterm Guide and the Monetra Client Interface
128  * Protocol Spec.
129  * \param[in] uniterm_conn Initialized connection to Uniterm
130  * as returned by uniterm_connect()
131  * \param[in] mparams Array of key/value parameters to send to
132  * Uniterm
133  * \return Hashtable of string key/value pairs from response. Please refer
134  * to the Uniterm Guide and Monetra Client Interface Protocol
135  * specification for the applicable list based on the action being
136  * performed. "code" and "u_errorcode" are always guaranteed to
137  * be returned.
138  */
139  static Hashtable uniterm_sendrequest(Monetra uniterm_conn, Hashtable mparams)
140  {
141      int id;
142
143      Hashtable response = new Hashtable();
144
145      /* Request a new transaction from libmonetra */
146      id = uniterm_conn.TransNew();
147
148      /* For each item in the params hashtable, add it to the transaction */
149      foreach (DictionaryEntry kv in mparams) {
150          uniterm_conn.TransKeyVal(id, (String)kv.Key, (String)kv.Value);
151      }
152
153      /* Send the request to the Uniterm. It will not return until
154      * a response is available, or a disconnect is detected */
155      if (!uniterm_conn.TransSend(id)) {
156          /* Disconnect detected, return an appropriate error condition!
157          * This should really never happen though... */
158          response["code"] = "DENY";
159          response["u_errorcode"] = "CONN_ERROR";
160          response["verbiage"] = "Connection to Uniterm failed: "
161                                + uniterm_conn.ConnectionError();
162          return response;
163      }
164
165      /* Save the response parameters from the Uniterm into a
166      * HashTable as our function prototype states. */
167      string[] keys = uniterm_conn.ResponseKeys(id);

```



```

168     for (int i=0; i < keys.Length; i++) {
169         response[keys[i]] = uniterm_conn.ResponseParam(id, keys[i]);
170     }
171
172     /* Free up some memory by purging unneeded data */
173     uniterm_conn.DeleteTrans(id);
174
175     return response;
176 }
177
178
179 /*! Tell Uniterm to shutdown. Since we start it up, we should make sure
180  * we turn it off prior to exiting otherwise the user will be prompted
181  * with an error message stating the Uniterm is already running on the
182  * next execution of this application!
183  * \param[in] uniterm_conn Initialized connection to the Uniterm
184  *                               as returned by uniterm_connect()
185  */
186 static void uniterm_shutdown(Monetra uniterm_conn)
187 {
188     Hashtable mparams = new Hashtable();
189     mparams["u_action"] = "shutdown";
190     uniterm_sendrequest(uniterm_conn, mparams);
191 }
192
193
194 /*! Main entry point to this application to be executed */
195 static void Main()
196 {
197     Monetra uniterm_conn;
198     string errorstr = "";
199     Hashtable response;
200
201     /* Step1: Launch the Uniterm */
202     uniterm_launch();
203     Console.WriteLine("Uniterm Launched");
204
205     /* Step2: Connect to the Uniterm */
206     uniterm_conn = uniterm_connect(ref errorstr);
207     if (uniterm_conn == null) {
208         Console.WriteLine("Failure: " + errorstr);
209         return;
210     }
211     Console.WriteLine("Connected to Uniterm");
212
213
214     /* Step3: Send txnrequest to Uniterm */
215     Hashtable mparams = new Hashtable();
216     /* Append the parameters for the txnrequest */
217     mparams["username"] = monetra_user;
218     mparams["password"] = monetra_pass;
219     mparams["u_action"] = "txnrequest";
220     mparams["u_devicetype"] = "ingenico_rba";
221     mparams["u_device"] = "USB";
222
223     /* Append the parameters for the transaction that will also get passed
224     * to Monetra such as the 'action', 'amount', etc. as described in the
225     * Monetra Client Interface Protocol Specification */

```

```

226     mparams["action"]    = "sale";
227     mparams["amount"]    = "12.00";
228     mparams["ordernum"]   = "123456";
229     mparams["comments"]   = "u_txnrequest";
230
231     response = uniterm_sendrequest(uniterm_conn, mparams);
232     if (String.Compare((string)response["code"], "AUTH", true) != 0) {
233         Console.WriteLine("Transaction failed.");
234     } else {
235         Console.WriteLine("Transaction SUCCESSFUL!");
236     }
237
238     /* Print out all the response key/value pairs ... */
239     foreach (DictionaryEntry kv in response) {
240         Console.WriteLine("\t" + (string)kv.Key + " = " + (string)kv.Value);
241     }
242
243     /* NOTE: No real reason to exit here ... we could just keep running
244      *        Step 3 all day long as long as you keep the uniterm_conn handle.
245      *        No reason to keep disconnecting and reconnecting, or
246      *        starting/stopping the Uniterm.
247      */
248
249     /* Step4: Cleanup */
250     uniterm_shutdown(uniterm_conn);
251
252     /* Connections will be automatically closed when the uniterm_conn
253      * initialized class is closed by the destructor/garbage
254      * collector */
255 }
256
257 }
258
259

```

C.2 Microsoft C# using XML and HttpWebRequest

```

1  /* Monetra Uniterm example program in C# using XML and HttpWebRequest
2  *
3  * Works with .Net Compact Framework v2
4  *
5  * Implemented based on the Monetra Uniterm Guide in conjunction with the
6  * Monetra Client Interface Protocol Specification
7  *
8  * Please contact support@monetra.com with any questions
9  */
10 using System;
11 using System.Diagnostics;
12 using System.Collections.Generic;
13 using System.Text;
14 using System.IO;
15 using System.Threading;
16 using System.Collections;
17 using System.Net;
18 using System.Xml;
19 using System.ComponentModel;

```

```

20 using System.Windows.Forms;
21 using System.Security.Cryptography.X509Certificates;
22
23 /* NOTE: if compiling with Mono, you can use
24 *      gmcs -r:System.Windows.Forms.dll utest_xml.cs
25 */
26
27 class utest_xml
28 {
29     /* Uniterm Connectivity Information
30     * NOTE: this is the default, it is possible to change, but 99%
31     *       of deployments will probably use this Uniterm information
32     *       as-is
33     */
34     private const string uniterm_host = "localhost";
35     private const int    uniterm_port = 8123;
36
37     /* Authentication information
38     * NOTE: This information corresponds with the public test server
39     *       at testbox.monetra.com:8665 */
40     private const string monetra_user = "test_retail:public";
41     private const string monetra_pass = "publ1ct3st";
42
43
44     static string uniterm_path()
45     {
46         switch (Environment.OSVersion.Platform) {
47             case PlatformID.Win32NT:
48             case PlatformID.Win32S:
49             case PlatformID.Win32Windows:
50             case PlatformID.WinCE:
51                 return "C:\\Program Files\\Main Street Softworks\\Monetra Uniterm\\monetra_uniterm.exe";
52             default:
53                 return "/usr/local/monetra/bin/monetra_uniterm";
54         }
55     }
56
57
58     /*! Function to launch Uniterm from the current process.
59     *   If we don't launch it from the current process, it won't be given
60     *   focus! (at least on Windows this is true, until the first
61     *   manual focus is performed by an end-user) */
62     static void uniterm_launch()
63     {
64         Process monetra_uniterm = new Process();
65         monetra_uniterm.StartInfo.FileName = uniterm_path();
66         /* Not supported on CE
67         *   monetra_uniterm.StartInfo.CreateNoWindow = true;
68         */
69
70         monetra_uniterm.Start();
71
72         /* Make sure Uniterm is ready before returning,
73         *   Sleep 1000ms (1s) */
74         System.Threading.Thread.Sleep(1000);
75     }
76
77

```

```

78  /*! Trust all SSL server certificates */
79  internal class AcceptAllCertificatePolicy : ICertificatePolicy
80  {
81      public AcceptAllCertificatePolicy()
82      {
83      }
84      public bool CheckValidationResult(ServicePoint sPoint,
85                                     X509Certificate cert,
86                                     WebRequest wRequest, int certProb)
87      {
88          // *** Always accept
89          return true;
90      }
91  }
92
93
94  /*! Function to POST and XML message to a Monetra-like entity
95  * (Monetra or Uniterm) via HTTPS. It will return
96  * the key/value pairs from the XML response
97  * \param[in] host      Host to connect to
98  * \param[in] port      Port to connect to (via SSL/HTTPS)
99  * \param[in] xml       String-form XML to post
100 * \return True on successful communication, False if communication failed.
101 *      Note: True doesn't mean the transaction itself was successful.
102 */
103 static Hashtable uniterm_https_post(string host, int port, string xml)
104 {
105     Hashtable      response = new Hashtable();
106     string          url      = "https://" + host + ":" + port.ToString();
107     HttpWebRequest req      = (HttpWebRequest)WebRequest.Create(url);
108     string          xmlout;
109
110     try {
111         /* POST Request */
112
113         /* Disable SSL Server Certificate Checking */
114         System.Net.ServicePointManager.CertificatePolicy =
115             new AcceptAllCertificatePolicy();
116
117         byte[] bytes;
118         bytes          = System.Text.Encoding.ASCII.GetBytes(xml);
119         req.Method      = "POST";
120         req.ContentType = "text/xml";
121         req.ContentLength = bytes.Length;
122         Stream reqStream = req.GetRequestStream();
123         reqStream.Write(bytes, 0, bytes.Length);
124         reqStream.Close();
125
126         /* Read Response */
127         /* Note issues with .Net CF v2 as per below:
128         *   http://blogs.msdn.com/b/andrewarnottms/archive/2007/11/19/why-net-compact-framework-fa
129         *   http://support.microsoft.com/kb/970549
130         * If the Server is OpenSSL, this can be worked around by setting
131         *   SSL_OP_DONT_INSERT_EMPTY_FRAGMENTS
132         */
133         HttpWebResponse resp = (HttpWebResponse)req.GetResponse();
134         Stream respStream    = resp.GetResponseStream();
135         StreamReader rdr     = new StreamReader(respStream);

```

```

136     xmlout                = rdr.ReadToEnd();
137     rdr.Close();
138 } catch (System.Net.WebException e) {
139     response["code"]       = "DENY";
140     response["u_errorcode"] = "CONN_ERROR";
141     response["verbiage"]    = "Connection to " + url + " failed: " +
142                             e.Message;
143     return response;
144 }
145 XmlDocument    xmldoc      = new XmlDocument();
146 xmldoc.LoadXml(xmlout);
147
148 XmlNodeList    trans       = xmldoc.DocumentElement.
149                             SelectSingleNode("Resp").ChildNodes;
150 foreach (XmlNode kv in trans) {
151     response[kv.Name] = kv.InnerText;
152 }
153 return response;
154 }
155
156
157 /*! Request a ttransaction from Uniterm as documented in the Monetra
158 * Uniterm Guide. The Key/Value pair params are a combination of the
159 * Parameters as documented in the Uniterm Guide and the Monetra Client
160 * Interface Protocol Spec.
161 * \param[in] mparams Array of key/value parameters to send to Uniterm
162 * \return Hashtable of string key/value pairs from response. Please refer
163 * to the Uniterm Guide and Monetra Client Interface Protocol
164 * specification for the applicable list based on the action being
165 * performed. "code" and "u_errorcode" are always guaranteed to
166 * be returned.
167 */
168 static Hashtable uniterm_sendrequest(Hashtable mparams)
169 {
170     string XML;
171
172     XML = "<MonetraTrans>" +
173          "<Trans identifier='1'>";
174
175     /* For each item in the params hashtable, add it to the transaction */
176     foreach (DictionaryEntry kv in mparams) {
177         XML = XML + "<" + (String)kv.Key + ">" + (String)kv.Value + "</" +
178              (string)kv.Key + ">";
179     }
180
181     XML = XML + "</Trans></MonetraTrans>";
182
183     return uniterm_https_post(uniterm_host, uniterm_port, XML);
184 }
185
186
187 /*! Tell Uniterm to shutdown. Since we start it up,
188 * we should make sure we turn it off prior to exiting otherwise
189 * the user will be prompted with an error message stating
190 * Uniterm is already running on the next execution
191 * of this application!
192 */
193 static void uniterm_shutdown()

```

```

194  {
195      Hashtable mparams = new Hashtable();
196      mparams["u_action"] = "shutdown";
197      uniterm_sendrequest(mparams);
198  }
199
200
201  /*! Main entry point to this application to be executed */
202  static void Main()
203  {
204      Hashtable response;
205
206      /* Step1: Launch Uniterm */
207      uniterm_launch();
208      MessageBox.Show("Uniterm Launched");
209
210
211      /* Step2: Send txnrequest to Uniterm */
212      Hashtable mparams = new Hashtable();
213      /* Append the parameters for the ticket request as per the Monetra
214       * Uniterm Guide, section 4 */
215      mparams["username"]      = monetra_user;
216      mparams["password"]      = monetra_pass;
217      mparams["u_action"]      = "txnrequest";
218      mparams["u_devicetype"]  = "ingenico_rba";
219      mparams["u_device"]      = "USB";
220
221      /* Append the parameters for the transaction that will also get passed
222       * to Monetra such as the 'action', 'amount', etc. as described in the
223       * Monetra Client Interface Protocol Specification */
224      mparams["action"]        = "sale";
225      mparams["amount"]        = "12.00";
226      mparams["ordernum"]      = "123456";
227      mparams["comments"]      = "u_txnrequest";
228
229      response = uniterm_sendrequest(mparams);
230      string resultMsg = "";
231      if (String.Compare((string)response["code"], "AUTH", true) != 0) {
232          resultMsg = "Transaction failed.\r\n";
233      } else {
234          resultMsg = "Transaction SUCCESSFUL!\r\n";
235      }
236
237      /* Print out all the response key/value pairs ... */
238      foreach (DictionaryEntry kv in response) {
239          resultMsg = resultMsg + (string)kv.Key + " = " + (string)kv.Value +
240              "\r\n";
241      }
242
243      MessageBox.Show(resultMsg);
244
245      /* NOTE: No real reason to exit here ... we could just keep running
246       *       Step 2 all day long as long.
247       *       No reason to keep starting/stopping Uniterm.
248       */
249
250      /* Step3: Cleanup */
251      uniterm_shutdown();

```

```

252
253     /* Connections will be automatically closed when the uniterm_conn
254     * initialized class is closed by the destructor/garbage
255     * collector */
256 }
257 }
258

```

C.3 Java using libmonetra

```

1  /* Uniterm example program in Java
2  *
3  * Depends on the libmonetra Java native API
4  *
5  * Implemented based on the Monetra Uniterm Guide in conjunction with the
6  * Monetra Client Interface Protocol Specification
7  *
8  * Please contact support@monetra.com with any questions
9  */
10 import java.util.Hashtable;
11 import java.util.Enumeraion;
12 import com.mainstreetsoftworks.MONETRA;
13
14 /* Compile/run with:
15 *   javac -classpath MONETRA.jar utest.java
16 *   java -cp "./MONETRA.jar:." utest
17 */
18
19 class utest {
20     /* Uniterm Connectivity Information
21     * NOTE: this is the default, it is possible to change, but 99%
22     *       of deployments will probably use this uniterm information
23     *       as-is
24     */
25     private static String uniterm_host      = "localhost";
26     private static int    uniterm_port      = 8123;
27
28     /* Authentication information
29     * NOTE: This information corresponds with the public test server
30     *       at testbox.monetra.com:8665 */
31     private static String monetra_user      = "test_retail:public";
32     private static String monetra_pass      = "publ1ct3st";
33
34
35     static String uniterm_path()
36     {
37         if (System.getProperty("os.name").startsWith("Windows")) {
38             return "C:\\Program Files\\Main Street Softworks\\Monetra Uniterm\\monetra_uniterm.exe";
39         } else {
40             return "/usr/local/monetra/bin/monetra_uniterm";
41         }
42     }
43
44
45     /*! Function to launch Uniterm from the current process. If we don't
46     *   launch it from the current process, it won't be given focus!

```

```

47  * (at least on Windows this is true, until the first manual focus is
48  * performed by an end-user) */
49  static void uniterm_launch()
50  {
51      try {
52          Process p = new ProcessBuilder(uniterm_path()).start();
53      } catch (java.io.IOException e) {
54          System.out.println(e.getMessage());
55          System.exit(1);
56      }
57      /* Make sure Uniterm is ready before returning,
58       * Sleep 1000ms (1s) */
59      try {
60          Thread.sleep(1000);
61      } catch (InterruptedException e) {
62      }
63  }
64
65
66  /*! Function to connect to an endpoint which uses the standard 'monetra'
67   * style protocol (so either Monetra itself, or Uniterm)
68   * \param[in] host      Resolvable hostname or IP address to connect to
69   * \param[in] port      Port associated with hostname to establish an SSL
70   *                      connection to
71   * \param[out] errorstr Textual error message if returns null
72   * \return Initialized connection class on success. null on failure
73   */
74  static MONETRA uniterm_connect_host(String host, int port,
75                                     StringBuilder errorstr)
76  {
77      /* Initialize the Class */
78      MONETRA conn = new MONETRA("");
79
80      errorstr.setLength(0);
81
82      /* We always want to use an SSL connection to Monetra and Uniterm */
83      conn.SetSSL(host, port);
84
85      /* Do not verify the SSL certificate, Monetra and Uniterm
86       * use self-signed certificates by default which cannot be validated.
87       * The connection is still encrypted, the endpoint just isn't strictly
88       * validated */
89      conn.VerifySSLCert(0);
90
91      /* This makes it so TransSend() will block until a response is
92       * received from Monetra. Simplifies the API since we will never
93       * have more than one outstanding transaction per connection in
94       * this application */
95      conn.SetBlocking(1);
96
97      /* Connect! */
98      if (conn.Connect() == 0) {
99          errorstr.append(conn.ConnectionError());
100         return null;
101     }
102
103     return conn;
104 }

```



```

105
106
107  /*! Wrapper function to connect to Uniterm
108   * \param[out] errorstr Textual error message if returns null
109   * \return Initialized connection class on success. null on failure
110   */
111  static MONETRA uniterm_connect(StringBuilder errorstr)
112  {
113      MONETRA conn;
114      StringBuilder myerror = new StringBuilder();
115      conn = uniterm_connect_host(uniterm_host, uniterm_port, myerror);
116      if (conn == null) {
117          errorstr.setLength(0);
118          errorstr.append("Connection to Uniterm Failed: " +
119                          myerror.toString());
120      }
121      return conn;
122  }
123
124
125  /*! Request a transaction from Uniterm as documented in the Monetra
126   * Uniterm Guide. The Key/Value pair params are a combination of the
127   * Parameters as documented in the Uniterm Guide and the Monetra Client
128   * Interface Protocol Spec.
129   * \param[in] uniterm_conn Initialized connection to Uniterm
130   *                                     as returned by uniterm_connect()
131   * \param[in] mparams      Array of key/value parameters to send to
132   *                                     Uniterm
133   * \return Hashtable of string key/value pairs from response. Please refer
134   *         to the Uniterm Guide and Monetra Client Interface Protocol
135   *         specification for the applicable list based on the action being
136   *         performed. "code" and "u_errorcode" are always guaranteed to
137   *         be returned.
138   */
139  static Hashtable<String,String> uniterm_sendrequest(MONETRA uniterm_conn,
140      Hashtable<String,String> mparams)
141  {
142      long id;
143
144      Hashtable response = new Hashtable<String,String>();
145
146      /* Request a new transaction from libmonetra */
147      id = uniterm_conn.TransNew();
148
149      /* For each item in the params hashtable, add it to the transaction */
150      for (String key : mparams.keySet()) {
151          String value = mparams.get(key);
152          uniterm_conn.TransKeyVal(id, key, value);
153      }
154
155      /* Send the request to the Uniterm. It will not return until
156       * a response is available, or a disconnect is detected */
157      if (uniterm_conn.TransSend(id) == 0) {
158          /* Disconnect detected, return an appropriate error condition!
159           * This should really never happen though... */
160          response.put("code", "DENY");
161          response.put("u_errorcode", "CONN_ERROR");
162          response.put("verbiage", "Connection to Uniterm failed:");

```

```

163                                     + uniterm_conn.ConnectionError());
164     return response;
165 }
166
167 /* Save the response parameters from the Uniterm into a
168  * Hashtable as our function prototype states. */
169 String[] keys = uniterm_conn.ResponseKeys(id);
170 for (int i=0; i < keys.length; i++) {
171     response.put(keys[i], uniterm_conn.ResponseParam(id, keys[i]));
172 }
173
174 /* Free up some memory by purging unneeded data */
175 uniterm_conn.DeleteTrans(id);
176
177 return response;
178 }
179
180
181 /*! Tell Uniterm to shutdown. Since we start it up,
182  * we should make sure we turn it off prior to exiting otherwise
183  * the user will be prompted with an error message stating the
184  * Uniterm is already running on the next execution
185  * of this application!
186  * \param[in] uniterm_conn Initialized connection to Uniterm
187  *                               as returned by uniterm_connect()
188  */
189 static void uniterm_shutdown(MONETRA uniterm_conn)
190 {
191     Hashtable mparams = new Hashtable<String,String>();
192     mparams.put("u_action", "shutdown");
193     uniterm_sendrequest(uniterm_conn, mparams);
194 }
195
196
197 /*! Main entry point to this application to be executed */
198 public static void main(String[] args)
199 {
200     MONETRA                uniterm_conn;
201     StringBuilder          errorstr = new StringBuilder();
202     Hashtable<String,String> response;
203     String                 ticket;
204
205     /* Step1: Launch Uniterm */
206     uniterm_launch();
207     System.out.println("Uniterm Launched");
208
209     /* Step2: Connect to Uniterm */
210     uniterm_conn = uniterm_connect(errorstr);
211     if (uniterm_conn == null) {
212         System.out.println("Failure: " + errorstr.toString());
213         return;
214     }
215     System.out.println("Connected to Uniterm");
216
217     /* Step3: Send a txnrequest to Uniterm */
218     Hashtable<String,String> mparams = new Hashtable<String,String>();
219     /* Append the parameters for the txnrequest */
220     mparams.put("username",    monetra_user);

```

```

221     mparams.put("password",    monetra_pass);
222     mparams.put("u_action",    "txnrequest");
223
224     mparams.put("u_devicetype", "ingenico_rba");
225     mparams.put("u_device",    "USB");
226
227     /* Append the parameters for the transaction that will also get passed
228      * to Monetra such as the 'action', 'amount', etc. as described in the
229      * Monetra Client Interface Protocol Specification */
230     mparams.put("action",    "sale");
231     mparams.put("amount",    "12.00");
232     mparams.put("ordernum",  "123456");
233     mparams.put("comments",  "u_txnrequest");
234
235     response = uniterm_sendrequest(uniterm_conn, mparams);
236     if (!response.get("code").equalsIgnoreCase("AUTH")) {
237         System.out.println("Transasction failed.");
238     } else {
239         System.out.println("Transasction SUCCESSFUL!");
240     }
241
242     /* Print out all the response key/value pairs ... */
243     for (String key : response.keySet()) {
244         String value = response.get(key);
245         System.out.println("\t" + key + " = " + value);
246     }
247
248     /* NOTE: No real reason to exit here ... we could just keep running
249      *         Step 3 all day long as long as you keep the uniterm_conn handle.
250      *         No reason to keep disconnecting and reconnecting, or
251      *         starting/stopping the Uniterm.
252      */
253
254     /* Step4: Cleanup */
255     uniterm_shutdown(uniterm_conn);
256
257     /* Connections will be automatically closed when the uniterm_conn
258      * initialized classe is closed by the destructor/garbage
259      * collector */
260 }
261
262 }
263
264

```

C.4 PHP using libmonetra

```

1  <?php
2  /* Monetra Uniterm example program in PHP
3   *
4   * Depends on the libmonetra PHP native API
5   *
6   * Implemented based on the Monetra Uniterm Guide in conjunction with the
7   * Monetra Client Interface Protocol Specification
8   *
9   * Please contact support@monetra.com with any questions

```

```

10  */
11  error_reporting(E_ALL);
12  require_once("libmonetra.php");
13
14
15
16  /* Uniterm Connectivity Information
17  * NOTE: this is the default, it is possible to change, but 99%
18  *       of deployments will probably use this uniterm information
19  *       as-is
20  */
21  $uniterm_host      = "localhost";
22  $uniterm_port      = 8123;
23
24  /* Authentication information
25  * NOTE: This information corresponds with the public test server
26  *       at testbox.monetra.com:8665 */
27  $monetra_user      = "test_retail:public";
28  $monetra_pass      = "publlct3st";
29
30
31  /* Sets the path of the Uniterm executable.  Currently using
32  * the default locations */
33  if (strtoupper(substr(PHP_OS, 0, 3)) === 'WIN') {
34  /* Windows path */
35  $uniterm_path      = "C:\\Program Files\\Main Street Softworks\\Monetra Uniterm\\monetra_u
36  } else {
37  /* Unix path */
38  $uniterm_path      = "/usr/local/monetra/bin/monetra_uniterm";
39  }
40
41
42  /*! Function to launch Uniterm from the current process.
43  * If we don't launch it from the current process, it won't be given
44  * focus! (at least on Windows this is true, until the first
45  * manual focus is performed by an end-user) */
46  function uniterm_launch()
47  {
48  global $uniterm_path;
49  if (class_exists("COM")) {
50  /* Must be running windows */
51  $WshShell = new COM("WScript.Shell");
52  $oExec    = $WshShell->Run('"' . $uniterm_path . '"', 10, false);
53  } else {
54  /* Must be on a Unix system */
55  system('"' . $uniterm_path . '" . " > /dev/null 2>&1 &");
56  }
57
58  /* Make sure Uniterm is ready before returning,
59  * sleep 2s */
60  sleep(2);
61  }
62
63
64  /*! Function to connect to an endpoint which uses the standard 'monetra'
65  * style protocol (so either Monetra itself, or Uniterm)
66  * \param[in] host      Resolvable hostname or IP address to connect to
67  * \param[in] port      Port associated with hostname to establish an SSL

```

```

68      *                               connection to
69      * \param[out] errorstr Textual error message if returns null
70      * \return Initialized connection on success. null on failure
71      */
72  function uniterm_connect_host($host, $port, &$errorstr)
73  {
74      /* Initialize the Connection */
75      $conn = M_InitConn();
76
77      $errorstr = "";
78
79      /* We always want to use an SSL connection to Monettra and Uniterm */
80      M_SetSSL($conn, $host, $port);
81
82      /* Do not verify the SSL certificate, Monettra and Uniterm
83      * use self-signed certificates by default which cannot be validated.
84      * The connection is still encrypted, the endpoint just isn't strictly
85      * validated */
86      M_VerifySSLCert($conn, false);
87
88      /* This makes it so TransSend() will block until a response is
89      * received from Monettra. Simplifies the API since we will never
90      * have more than one outstanding transaction per connection in
91      * this application */
92      M_SetBlocking($conn, true);
93
94      /* Connect! */
95      if (!M_Connect($conn)) {
96          $errorstr = M_ConnectionError($conn);
97          return null;
98      }
99
100     return $conn;
101 }
102
103
104 /*! Wrapper function to connect to Uniterm
105 * \param[out] errorstr Textual error message if returns null
106 * \return Initialized connection on success. null on failure
107 */
108 function uniterm_connect(&$errorstr)
109 {
110     global $uniterm_host, $uniterm_port;
111
112     $myerror = "";
113     $conn = uniterm_connect_host($uniterm_host, $uniterm_port, &$myerror);
114     if ($conn == null) {
115         $errorstr = "Connection to Uniterm Failed: " . $myerror;
116     }
117     return $conn;
118 }
119
120
121 /*! Request a transaction from Uniterm as documented in the Uniterm Guide.
122 * The Key/Value pair params are a combination of the Parameters as
123 * documented in the Uniterm Guide and the Monettra Client Interface Protocol
124 * Spec.
125 * \param[in] uniterm_conn Initialized connection to Uniterm as returned by

```

```

126 *                               uniterm_connect()
127 * \param[in] params           Array of key/value parameters to send to Uniterm
128 *
129 * \return Array of string key/value pairs from response. Please refer to the
130 *         Uniterm Guide and Monetra Client Interface Protocol specification
131 *         for the applicable list based on the action being performed.
132 *         "code" and "u_errorcode" are always guaranteed to be returned.
133 */
134 function uniterm_sendrequest($uniterm_conn, $params)
135 {
136     $response = array();
137
138     /* Request a new transaction from libmonetra */
139     $id = M_TransNew($uniterm_conn);
140
141     /* For each item in the params array, add it to the transaction */
142     foreach ($params as $key => $value) {
143         M_TransKeyVal($uniterm_conn, $id, $key, $value);
144     }
145
146     /* Send the request to the Uniterm. It will not return until a
147     * response is available, or a disconnect is detected */
148     if (!M_TransSend($uniterm_conn, $id)) {
149         /* Disconnect detected, return an appropriate error condition!
150         * This should really never happen though... */
151         $response["code"] = "DENY";
152         $response["u_errorcode"] = "CONN_ERROR";
153         $response["verbiage"] = "Connection to Uniterm failed: " .
154                               M_ConnectionError($uniterm_conn);
155         return $response;
156     }
157
158     /* Save the response parameters from the Uniterm into a HashTable
159     * as our function prototype states. */
160     $keys = M_ResponseKeys($uniterm_conn, $id);
161     foreach ($keys as $value) {
162         $response[$value] = M_ResponseParam($uniterm_conn, $id, $value);
163     }
164
165     /* Free up some memory by purging unneeded data */
166     M_DeleteTrans($uniterm_conn, $id);
167
168     return $response;
169 }
170
171
172 /*! Tell Uniterm to shutdown. Since we start it up,
173 * we should make sure we turn it off prior to exiting otherwise
174 * the user will be prompted with an error message stating the
175 * Uniterm is already running on the next execution
176 * of this application!
177 * \param[in] uniterm_conn Initialized connection to Uniterm
178 *                       as returned by uniterm_connect()
179 */
180 function uniterm_shutdown($uniterm_conn)
181 {
182     uniterm_sendrequest($uniterm_conn, array("u_action" => "shutdown"));
183 }

```

```

184
185
186
187  /* CODE TO EXECUTE ... */
188
189  $errorstr = "";
190
191  /* Step1: Launch Uniterm */
192  uniterm_launch();
193  echo "Uniterm Launched\r\n";
194
195  /* Step2: Connect to Uniterm */
196  $uniterm_conn = uniterm_connect(&$errorstr);
197  if ($uniterm_conn == null) {
198      echo "Failure: " . $errorstr . "\r\n";
199      return;
200  }
201
202  echo "Connected to Uniterm\r\n";
203
204
205  /* Step3: Send a txnrequest to the Uniterm */
206  $params = array();
207
208  /* Append the parameters for the txnrequest */
209  $params["username"] = $monetra_user;
210  $params["password"] = $monetra_pass;
211  $params["u_action"] = "txnrequest";
212  $params["u_devicetype"] = "ingenico_rba";
213  $params["u_device"] = "USB";
214
215  /* Append the parameters for the transaction that will also get passed to
216   * Monetra such as the 'action', 'amount', etc. as described in the Monetra
217   * Client Interface Protocol Specification */
218  $params['action'] = 'sale';
219  $params['amount'] = '12.00';
220  $params['ordernum'] = '123456';
221  $params['comments'] = 'u_txnrequest';
222
223  $response = uniterm_sendrequest($uniterm_conn, $params);
224  if (strcasecmp($response["code"], "AUTH") != 0) {
225      echo "Transaction Failed.\r\n";
226  } else {
227      echo "Transaction SUCCESSFUL!\r\n";
228  }
229
230  /* Print out all the response key/value pairs ... */
231  foreach ($response as $key => $value) {
232      echo "\t" . $key . " = " . $value . "\r\n";
233  }
234
235  /* NOTE: No real reason to exit here ... we could just keep running
236   * Step 3 all day long as long as you keep the uniterm_conn handle.
237   * No reason to keep disconnecting and reconnecting, or
238   * starting/stopping Uniterm.
239   */
240
241  /* Step4: Cleanup */

```

```

242 uniterm_shutdown($uniterm_conn);
243
244 /* Connections will be automatically closed when the uniterm_conn
245    * initialized connection is closed by the destructor/garbage collector */
246
247 ?>
248
249

```

C.5 Microsoft VB.Net using libmonetra

```

1  ' Monetra Uniterm example program in VB.Net
2  '
3  ' Depends on the libmonetra C# .Net native API (DLL)
4  '
5  ' Implemented based on the Monetra Uniterm Guide in conjunction with the
6  ' Monetra Client Interface Protocol Specification
7  '
8  ' Please contact support@monetra.com with any questions
9
10 Option Explicit On
11 Option Strict On
12
13 Imports System
14 Imports System.Collections
15 Imports System.Diagnostics
16 Imports System.Threading
17 Imports libmonetra
18
19 ' On unix, compile using:
20 '   gmcs /target:library /unsafe libmonetra.cs
21 '   vbnc2 -r:libmonetra.dll utest.vb
22
23 Module Module1
24     ' Uniterm Connectivity Information
25     ' NOTE: this is the default, it is possible to change, but 99%
26     '       of deployments will probably use this Uniterm information
27     '       as-is
28     Private Const uniterm_host As String = "localhost"
29     Private Const uniterm_port As Integer = 8123
30
31     ' Authentication information
32     ' NOTE: This information corresponds with the public test server
33     '       at testbox.monetra.com:8665
34     Private Const monetra_user As String = "test_retail:public"
35     Private Const monetra_pass As String = "publlct3st"
36
37     Private Function uniterm_path As String
38         Select Case Environment.OSVersion.Platform
39             Case PlatformID.Win32NT, PlatformID.Win32S, _
40                 PlatformID.Win32Windows, PlatformID.WinCE
41                 Return "C:\\Program Files\\Main Street Softworks\\Monetra Uniterm\\monetra_uniterm.exe"
42             Case Else
43                 Return "/usr/local/monetra/bin/monetra_uniterm"
44         End Select
45     End Function

```



```

46
47
48 ' ! Function to launch Uniterm from the current process.
49 '   If we don't launch it from the current process, it won't be given
50 '   focus! (at least on Windows this is true, until the first
51 '   manual focus is performed by an end-user)
52 Private Sub uniterm_launch()
53     Dim monetra_uniterm As New Process()
54     monetra_uniterm.StartInfo.FileName = uniterm_path
55     monetra_uniterm.StartInfo.CreateNoWindow = True
56
57     monetra_uniterm.Start()
58
59     ' Make sure Uniterm is ready before returning,
60     ' Sleep 1000ms (1s)
61     System.Threading.Thread.Sleep(1000)
62 End Sub
63
64
65 ' ! Function to connect to an endpoint which uses the standard 'monetra'
66 '   style protocol (so either Monetra itself, or Uniterm)
67 '   \param[in] host      Resolvable hostname or IP address to connect to
68 '   \param[in] port      Port associated with hostname to establish an SSL
69 '                       connection to
70 '   \param[out] errorstr Textual error message if returns null
71 '   \return Initialized connection class on success. null on failure
72 Private Function uniterm_connect_host(ByVal host As String, ByVal port _
73                                     As Integer, ByRef errorstr As String) _
74                                     As Monetra
75     ' Initialize the Class
76     Dim conn As New Monetra
77
78     errorstr = ""
79
80     ' We always want to use an SSL connection to Monetra and Uniterm
81     conn.SetSSL(host, port)
82
83     ' Do not verify the SSL certificate, Monetra and Uniterm
84     ' use self-signed certificates by default which cannot be validated.
85     ' The connection is still encrypted, the endpoint just isn't strictly
86     ' validated
87     conn.VerifySSLCert(False)
88
89     ' This makes it so TransSend() will block until a response is
90     ' received from Monetra. Simplifies the API since we will never
91     ' have more than one outstanding transaction per connection in
92     ' this application
93     conn.SetBlocking(True)
94
95     ' Connect!
96     If Not conn.Connect() Then
97         errorstr = conn.ConnectionError()
98         Return Nothing
99     End If
100
101     Return conn
102 End Function
103

```

```

104
105 ' ! Wrapper function to connect to the Uniterm
106 ' \param[out] errorstr Textual error message if returns null
107 ' \return Initialized connection class on success. null on failure
108 Private Function uniterm_connect(ByRef errorstr As String) As Monetra
109     Dim conn As Monetra
110     Dim myerror As String = ""
111     conn = uniterm_connect_host(uniterm_host, uniterm_port, myerror)
112     If conn Is Nothing Then
113         errorstr = "Connection to Uniterm Failed: " + myerror
114     End If
115
116     Return conn
117 End Function
118
119 ' Request a transaction from Uniterm as documented in the Uniterm Guide.
120 ' The Key/Value pair params are a combination of the Parameters as
121 ' documented in the Uniterm Guide and the Monetra Client Interface
122 ' Protocol Spec.
123 ' \param[in] uniterm_conn Initialized connection to the Uniterm
124 '                        as returned by uniterm_connect()
125 ' \param[in] mparams      Array of key/value parameters to send to Uniterm
126 ' \return Hashtable of string key/value pairs from response. Please refer
127 '         to the Uniterm Guide and Monetra Client Interface Protocol
128 '         specification for the applicable list based on the action being
129 '         performed. "code" and "u_errorcode" are always guaranteed to
130 '         be returned.
131 Private Function uniterm_sendrequest(ByVal uniterm_conn As Monetra, ByVal _
132                                     mparams As Hashtable) As Hashtable
133     Dim id As Integer
134     Dim response As New Hashtable
135
136     ' Request a new transaction from libmonetra
137     id = uniterm_conn.TransNew()
138
139     ' For each item in the params hashtable, add it to the transaction
140     Dim kv As DictionaryEntry
141     For Each kv In mparams
142         uniterm_conn.TransKeyVal(id, CType(kv.Key, String), _
143                                     CType(kv.Value, String))
144     Next kv
145
146     ' Send the request to the Uniterm. It will not return until a
147     ' response is available, or a disconnect is detected
148     If Not uniterm_conn.TransSend(id) Then
149         ' Disconnect detected, return an appropriate error condition!
150         ' This should really never happen though...
151         response("code") = "DENY"
152         response("u_errorcode") = "CONN_ERROR"
153         response("verbiage") = "Connection to Uniterm failed:" _
154                               + uniterm_conn.ConnectionError()
155     End If
156     Return response
157
158     ' Save the response parameters from Uniterm into a
159     ' HashTable as our function prototype states. */
160     Dim keys() As String = uniterm_conn.ResponseKeys(id)
161     Dim i As Integer

```

```

162     For i = 0 To keys.Length - 1
163         response(keys(i)) = uniterm_conn.ResponseParam(id, keys(i))
164     Next i
165
166     ' Free up some memory by purging unneeded data
167     uniterm_conn.DeleteTrans(id)
168
169     Return response
170 End Function
171
172
173 ' ! Tell Uniterm to shutdown. Since we start it up,
174 ' we should make sure we turn it off prior to exiting otherwise
175 ' the user will be prompted with an error message stating the
176 ' Uniterm is already running on the next execution
177 ' of this application!
178 ' \param[in] uniterm_conn Initialized connection to Uniterm
179 ' as returned by uniterm_connect()
180 Private Sub uniterm_shutdown(ByVal uniterm_conn As Monetra)
181     Dim mparams As New Hashtable
182
183     mparams("u_action") = "shutdown"
184     uniterm_sendrequest(uniterm_conn, mparams)
185 End Sub
186
187 ' ! Main entry point to this application to be executed
188 Public Sub Main()
189     Dim uniterm_conn As Monetra
190     Dim errorstr As String = ""
191     Dim response As Hashtable
192     Dim ticket As String
193
194     ' Step1: Launch Uniterm
195     uniterm_launch()
196     Console.WriteLine("Uniterm Launched")
197
198     ' Step2: Connect to Uniterm
199     uniterm_conn = uniterm_connect(errorstr)
200     If uniterm_conn Is Nothing Then
201         Console.WriteLine("Failure: " + errorstr)
202         Return
203     End If
204     Console.WriteLine("Connected to Uniterm")
205
206     ' Step3: Send a txnrequest to Uniterm
207     Dim mparams As New Hashtable
208     ' Append the parameters for the ticket request as per the Monetra
209     ' Uniterm Guide
210     mparams("username") = monetra_user
211     mparams("password") = monetra_pass
212     mparams("u_action") = "txnrequest"
213     mparams("u_devicetype") = "ingenico_rba"
214     mparams("u_device") = "USB"
215
216     ' Append the parameters for the transaction that will also get passed
217     ' to Monetra such as the 'action', 'amount', etc. as described in the
218     ' Monetra Client Interface Protocol Specification
219     mparams("action") = "sale"

```

```

220     mparams("amount")    = "12.00"
221     mparams("ordernum")   = "123456"
222     mparams("comments")   = "u_txnrequest"
223
224     response = uniterm_sendrequest(uniterm_conn, mparams)
225     If StrComp(CType(response("code"), String), "AUTH", _
226               vbTextCompare) <> 0 Then
227         Console.WriteLine("Transaction failed.")
228     Else
229         Console.WriteLine("Transaction SUCCESSFUL!")
230     End If
231
232     ' Print out all the response key/value pairs ...
233     Dim kv As DictionaryEntry
234     For Each kv In response
235         Console.WriteLine("  " + CType(kv.Key, String) + " = " + _
236                           CType(kv.Value, String))
237     Next kv
238
239     ' NOTE: No real reason to exit here ... we could just keep running
240     '       Step 3 all day long as long as you keep the uniterm_conn handle.
241     '       No reason to keep disconnecting and reconnecting, or
242     '       starting/stopping Uniterm.
243
244     ' Step4: Cleanup
245     uniterm_shutdown(uniterm_conn)
246
247     ' Connections will be automatically closed when the uniterm_conn
248     ' initialized class is closed by the destructor/garbage
249     ' collector
250 End Sub
251
252 End Module
253
254

```

C.6 Microsoft VBScript using XML and MSXML2

```

1  ' Monetra Uniterm example program in VBScript
2  '
3  ' Depends on the MSXML, and Microsoft Scripting Runtime
4  '
5  ' Implemented based on the Monetra Uniterm Guide in conjunction with the
6  ' Monetra Client Interface Protocol Specification
7  '
8  ' Please contact support@monetra.com with any questions
9
10 Option Explicit
11
12 ' Monetra Connectivity Information
13 Dim monetra_user
14 Dim monetra_pass
15
16 ' Uniterm Connectivity Information
17 Dim uniterm_host
18 Dim uniterm_port

```

```

19 Dim uniterm_path
20
21
22 '! Function to launch Uniterm from the current process.
23 ' If we don't launch it from the current process, it won't be given
24 ' focus! (at least on Windows this is true, until the first
25 ' manual focus is performed by an end-user)
26 Sub uniterm_launch()
27 Dim objShell
28 Dim res
29 Set objShell = CreateObject("Wscript.Shell")
30 res = objShell.Run(""" & uniterm_path & """, 10, FALSE)
31
32 ' Make sure Uniterm is ready before returning,
33 ' Sleep 1000ms (1s)
34 WScript.Sleep 1000
35 End Sub
36
37
38 '! Function to POST and XML message to a Monetra-like entity
39 ' (Monetra or the Uniterm) via HTTPS. It will return
40 ' the key/value pairs from the XML response
41 '\param[in] host Host to connect to
42 '\param[in] port Port to connect to (via SSL/HTTPS)
43 '\param[in] xml String-form XML to post
44 '\param[out] errorstr If returning False, the error message, typically comms
45 ' error
46 '\param[out] myresponse Dictionary of string key/value pairs from the response.
47 '\return True on successful communication, False if communication failed.
48 ' Note: True doesn't mean the transaction itself was successful.
49 Function uniterm_https_post(ByVal host, ByVal port, ByVal xml, ByRef errorstr, _
50 ByRef myresponse)
51 Dim xmlhttp
52 Dim xmldoc
53
54 Set xmlhttp = CreateObject("MSXML2.ServerXMLHTTP")
55
56 xmlhttp.open "POST", "https://" & host & ":" & port, False
57 xmlhttp.setOption 2, 13056
58 ' Set Timeouts (in milliseconds)
59 ' DNS: 5s, Connect: 5s, Send: 30s, Receive: 120s
60 xmlhttp.setTimeouts 5000, 5000, 30000, 120000
61 xmlhttp.setRequestHeader "Content-Type", "text/xml"
62
63 On Error Resume Next
64 xmlhttp.send xml
65
66 If Not Err.Number = 0 Then
67 errorstr = "HTTPS POST Failed to https://" & host & ":" & port & _
68 ":" & Err.Description
69 uniterm_https_post = False
70 Exit Function
71 End If
72
73 Set xmldoc = CreateObject("Microsoft.XMLDOM")
74
75 xmldoc.async = "false"
76 xmldoc.loadxml(xmlhttp.responseText)

```

```

77
78 Dim Trans
79 Set Trans = xmldoc.documentElement.selectSingleNode("Resp").childNodes
80
81 Dim kv
82 For Each kv In Trans
83     myresponse(kv.nodeName) = kv.text
84 Next
85
86 uniterm_https_post = True
87 End Function
88
89
90 '! Request a transaction from Uniterm as documented in the Uniterm Guide.
91 ' The Key/Value pair params are a combination of the Parameters as documented
92 ' the Uniterm Guide and the Monetra Client Interface Protocol Spec.
93 ' \param[in] mparams Dictionary of key/value parameters to send to the
94 ' Uniterm
95 ' \param[out] errorstr If returning False, the error message, typically comms
96 ' error
97 ' \param[out] myresponse Dictionary of string key/value pairs from response.
98 ' Please refer to the Uniterm Guide and Monetra Client
99 ' Interface Protocol specification for the applicable
100 ' list based on the action being performed. "code" and
101 ' "u_errorcode" are always guaranteed to be returned.
102 ' \return True on successful communication, False if communication failed.
103 ' Note: True doesn't mean the transaction itself was successful.
104 Function uniterm_sendrequest(ByVal mparams, ByRef errorstr, ByRef myresponse)
105 Dim xml
106
107 xml = "<MonetraTrans><Trans identifier='1'>"
108
109 ' For each item in the params dictionary, add it to the transaction
110 Dim key
111 For Each key In mparams
112     xml = xml & "<" & key & ">" & mparams(key) & "</" & key & ">"
113 Next
114
115 xml = xml & "</Trans></MonetraTrans>"
116
117 uniterm_sendrequest = uniterm_https_post(uniterm_host, uniterm_port, xml, _
118                                         errorstr, myresponse)
119 End Function
120
121
122 '! Tell Uniterm to shutdown. Since we start it up,
123 ' we should make sure we turn it off prior to exiting otherwise
124 ' the user will be prompted with an error message stating the
125 ' Uniterm is already running on the next execution
126 ' of this application!
127 Sub uniterm_shutdown()
128 Dim myresponse
129 Dim errorstr
130 Dim mparams
131
132 Set mparams = CreateObject("Scripting.Dictionary")
133 mparams("u_action") = "shutdown"
134

```

```

135  uniterm_sendrequest mparams, errorstr, myresponse
136  ' No need for error checking in this function as we don't
137  ' care if this fails
138 End Sub
139
140
141  '! Main entry point to this application to be executed
142
143  ' Uniterm Connectivity Information
144  ' NOTE: this is the default, it is possible to change, but 99%
145  '       of deployments will probably use this Uniterm information
146  '       as-is
147  uniterm_host = "localhost"
148  uniterm_port = 8123
149  uniterm_path = "C:\\Program Files\\Main Street Softworks\\Monetra Uniterm\\monetra_uniterm.exe"
150
151  ' Authentication information
152  ' NOTE: This information corresponds with the public test server
153  '       at testbox.monetra.com:8665
154  monetra_user = "test_retail:public"
155  monetra_pass = "publlct3st"
156
157
158  Dim errorstr
159  Dim mparams
160  Dim myresp
161  Dim msg
162
163  errorstr = ""
164
165  ' Step1: Launch Uniterm
166  uniterm_launch
167  MsgBox("Uniterm Launched")
168
169
170  ' Step2: Send txnrequest to Uniterm
171
172  Set myresp = CreateObject("Scripting.Dictionary")
173  Set mparams = CreateObject("Scripting.Dictionary")
174  ' Append the parameters for the txnrequest
175  mparams("username") = monetra_user
176  mparams("password") = monetra_pass
177  mparams("u_action") = "txnrequest"
178  mparams("u_devicetype") = "ingenico_rba"
179  mparams("u_device") = "USB"
180
181  ' Append the parameters for the transaction that will also get passed
182  ' to Monetra such as the 'action', 'amount', etc. as described in the
183  ' Monetra Client Interface Protocol Specification
184  mparams("action") = "sale"
185  mparams("amount") = "12.00"
186  mparams("ordernum") = "123456"
187  mparams("comments") = "u_txnrequest"
188
189  If Not uniterm_sendrequest(mparams, errorstr, myresp) Then
190  MsgBox errorstr
191  WScript.Quit 1
192 End If

```

```

193
194 If StrComp(myresp("code"), "AUTH", vbTextCompare) <> 0 Then
195     msg = "Transaction failed." & vbNewLine
196 Else
197     msg = "Transaction SUCCESSFUL!" & vbNewLine
198 End If
199
200 ' Print out all the response key/value pairs ...
201 Dim key
202 For Each key In myresp
203     msg = msg & "  " & key & " = " & myresp(key) & vbNewLine
204 Next
205
206 MsgBox (msg)
207
208
209 ' NOTE: No real reason to exit here ... we could just keep running
210 '       Step 2 all day long. No reason to keep starting/stopping the
211 '       Uniterm.
212
213 ' Step3: Cleanup
214 uniterm_shutdown
215
216
217
218
219

```

C.7 Microsoft Visual Basic 6 using libmonetra

```

1  Attribute VB_Name = "Module1"
2  ' Monetra Uniterm example program in VB6
3  '
4  ' Depends on the libmonetra C# .Net native API (DLL) (has COM hooks)
5  '
6  ' Must add reference to libmonetra and Microsoft Scripting Runtime
7  '
8  ' Implemented based on the Monetra Uniterm Guide in conjunction with the
9  ' Monetra Client Interface Protocol Specification
10 '
11 ' Please contact support@monetra.com with any questions
12
13 Option Explicit
14
15 ' MonetraInformation
16 Dim monetra_user As String
17 Dim monetra_pass As String
18
19 ' Uniterm Connectivity Information
20 Dim uniterm_host As String
21 Dim uniterm_port As Integer
22 Dim uniterm_path As String
23
24 Private Declare Sub Sleep Lib "kernel32.dll" (ByVal dwMilliseconds As Long)
25
26 '! Function to launch Uniterm from the current process.

```



```

27 ' If we don't launch it from the current process, it won't be given
28 ' focus! (at least on Windows this is true, until the first
29 ' manual focus is performed by an end-user)
30 Sub uniterm_launch()
31 Dim id As Double
32 id = Shell(""" & uniterm_path & """, vbNormalFocus)
33
34 ' Make sure Uniterm is ready before returning,
35 ' Sleep 1000ms (1s)
36 Sleep (1000)
37 End Sub
38
39
40 '! Function to connect to an endpoint which uses the standard 'monetra'
41 ' style protocol (so either Monetra itself, or Uniterm)
42 ' \param[in] host Resolvable hostname or IP address to connect to
43 ' \param[in] port Port associated with hostname to establish an SSL
44 ' connection to
45 ' \param[out] errorstr Textual error message if returns null
46 ' \return Initialized connection class on success. null on failure
47 Function uniterm_connect_host(ByVal host As String, ByVal port As Integer, _
48 ByRef errorstr As String) As IMonetra
49 ' Initialize the Class
50 Dim conn As IMonetra
51 Set conn = New Monetra
52
53 errorstr = ""
54
55 ' We always want to use an SSL connection to Monetra and Uniterm
56 conn.SetSSL host, port
57
58 ' Do not verify the SSL certificate, Monetra and Uniterm
59 ' use self-signed certificates by default which cannot be validated.
60 ' The connection is still encrypted, the endpoint just isn't strictly
61 ' validated
62 conn.VerifySSLCert False
63
64 ' This makes it so TransSend() will block until a response is
65 ' received from Monetra. Simplifies the API since we will never
66 ' have more than one outstanding transaction per connection in
67 ' this application
68 conn.SetBlocking True
69
70 ' Connect!
71 If Not conn.Connect() Then
72 errorstr = conn.ConnectionError()
73 Set uniterm_connect_host = Nothing
74 Exit Function
75 End If
76
77 Set uniterm_connect_host = conn
78 End Function
79
80
81 '! Wrapper function to connect to Uniterm
82 ' \param[out] errorstr Textual error message if returns null
83 ' \return Initialized connection class on success. null on failure
84 Function uniterm_connect(ByRef errorstr As String) As IMonetra

```

```

85 Dim conn As IMonetra
86 Dim myerror As String
87
88 myerror = ""
89 Set conn = uniterm_connect_host(uniterm_host, uniterm_port, myerror)
90 If conn Is Nothing Then
91     errorstr = "Connection to Uniterm Failed: " & myerror
92 End If
93 Set uniterm_connect = conn
94 End Function
95
96
97 ' Request a transaction from Uniterm as documented in the Monetra Uniterm
98 ' Guide. The Key/Value pair params are a combination of the Parameters as
99 ' Uniterm Guide and the Monetra Client Interface Protocol Spec.
100 ' \param[in] uniterm_conn Initialized connection to Unitermas returned by
101 '                           connect_to_uniterm()
102 ' \param[in] mparams       Dictionary of key/value parameters to send to
103 '                           Uniterm
104 ' \return Dictionary of string key/value pairs from response. Please refer
105 ' to the Uniterm Guide and Monetra Client Interface Protocol
106 ' specification for the applicable list based on the action being
107 ' performed. "code" and "u_errorcode" are always guaranteed to
108 ' be returned.
109 Function uniterm_sendrequest(ByVal uniterm_conn As IMonetra, _
110     ByVal mparams As Dictionary) _
111     As Dictionary
112 Dim id As Integer
113 Dim myresponse As New Dictionary
114
115 ' Request a new transaction from libmonetra
116 id = uniterm_conn.TransNew()
117
118 ' For each item in the params dictionary, add it to the transaction
119 Dim key
120 For Each key In mparams
121     uniterm_conn.TransKeyVal id, key, mparams(key)
122 Next key
123
124 ' Send the request to the Uniterm. It will not return until a
125 ' response is available, or a disconnect is detected
126 If Not uniterm_conn.TransSend(id) Then
127     ' Disconnect detected, return an appropriate error condition!
128     ' This should really never happen though...
129     myresponse("code") = "DENY"
130     myresponse("u_errorcode") = "CONN_ERROR"
131     myresponse("verbiage") = "Connection to Uniterm failed: " _
132         & uniterm_conn.ConnectionError()
133     Set uniterm_sendrequest = myresponse
134     Exit Function
135 End If
136
137 ' Save the response parameters from the Uniterm into a HashTable
138 ' as our function prototype states.
139 Dim keys() As String
140 keys = uniterm_conn.ResponseKeys(id)
141 Dim i As Integer
142 For i = LBound(keys) To UBound(keys)

```

```

143     myresponse(keys(i)) = uniterm_conn.ResponseParam(id, keys(i))
144     Next i
145
146     ' Free up some memory by purging unneeded data
147     uniterm_conn.DeleteTrans (id)
148
149     Set uniterm_sendrequest = myresponse
150 End Function
151
152
153 '! Tell Uniterm to shutdown. Since we start it up, we should make sure we
154 ' turn it off prior to exiting otherwise the user will be prompted with an
155 ' error message stating Uniterm is already running on the next execution
156 ' of this application!
157 ' \param[in] uniterm_conn Initialized connection to Uniterm as returned by
158 '         connect_to_uniterm()
159 Sub uniterm_shutdown(ByVal uniterm_conn As IMonetra)
160     Dim mparams As New Dictionary
161
162     mparams("u_action") = "shutdown"
163     uniterm_sendrequest uniterm_conn, mparams
164 End Sub
165
166
167 '! Main entry point to this application to be executed
168 Sub Main()
169     ' Uniterm Connectivity Information
170     ' NOTE: this is the default, it is possible to change, but 99%
171     '       of deployments will probably use this Uniterm information
172     '       as-is
173     uniterm_host = "localhost"
174     uniterm_port = 8123
175     uniterm_path = "C:\\Program Files\\Main Street Softworks\\Monetra Uniterm\\monetra_uniterm.ex
176
177     ' Authentication information
178     ' NOTE: This information corresponds with the public test server
179     '       at testbox.monetra.com:8665
180     monetra_user = "test_retail:public"
181     monetra_pass = "publlct3st"
182
183     Dim uniterm_conn As IMonetra
184     Dim errorstr As String
185     Dim myresp As Dictionary
186     Dim msg As String
187
188     errorstr = ""
189
190     ' Step1: Launch Uniterm
191     uniterm_launch
192     MsgBox ("Uniterm Launched")
193
194     ' Step2: Connect to Uniterm
195     Set uniterm_conn = uniterm_connect(errorstr)
196     If uniterm_conn Is Nothing Then
197         MsgBox ("Failure: " & errorstr)
198     Exit Sub
199 End If
200

```

```

201 MsgBox ("Connected to the Uniterm")
202
203 ' Step3: Send a txnrequest to Uniterm
204 Dim mparams As New Dictionary
205 ' Append the parameters for the ticket request as per the Uniterm Guide
206 mparams("username") = monetra_user
207 mparams("password") = monetra_pass
208 mparams("u_action") = "txnrequest"
209 mparams("u_devicetype") = "ingenico_rba"
210 mparams("u_device") = "USB"
211
212 ' Append the parameters for the transaction that will also get passed
213 ' to Monetra such as the 'action', 'amount', etc. as described in the
214 ' Monetra Client Interface Protocol Specification
215 mparams("action") = "sale"
216 mparams("amount") = "12.00"
217 mparams("ordernum") = "123456"
218 mparams("comments") = "u_txnrequest"
219
220 Set myresp = uniterm_sendrequest(uniterm_conn, mparams)
221 If StrComp(myresp("code"), "AUTH", vbTextCompare) <> 0 Then
222     msg = "Transaction failed." & vbNewLine
223 Else
224     msg = "Transaction SUCCESSFUL!" & vbNewLine
225 End If
226
227 ' Print out all the response key/value pairs ...
228 Dim key
229 For Each key In myresp
230     msg = msg & " " & key & " = " & myresp(key) & vbNewLine
231 Next key
232 MsgBox (msg)
233
234 ' NOTE: No real reason to exit here ... we could just keep running
235 '       Step 3 all day long as long as you keep the uniterm_conn handle.
236 '       No reason to keep disconnecting and reconnecting, or
237 '       starting/stopping Uniterm.
238
239 ' Step4: Cleanup
240 uniterm_shutdown uniterm_conn
241
242 ' Connections will be automatically closed when the uniterm_conn initialized
243 ' class is cleaned up by the destructor/garbage collector
244 End Sub
245
246
247

```

D PCI Security and Implementation

The below details the various security and PCI requirements and how deployments may be impacted. Integrators and distributors should read this section prior to any production deployments.

TOPIC	DISCUSSION
Delete sensitive authentication data stored by previous payment application versions.	UniTerm has never stored any sensitive authentication data.
Delete any sensitive authentication data (pre-authorization) gathered as a result of troubleshooting the payment application.	UniTerm has never stored any sensitive authentication data, even for troubleshooting purposes.
Securely delete cardholder data after customer-defined retention period.	UniTerm never stores cardholder data.
Mask PAN when displayed so only personnel with a business need can see the full PAN.	UniTerm mandates the use of users with the <code>obscured</code> flag, therefore it is not possible that the full PAN can ever be returned.
Render PAN unreadable anywhere it is stored (including data on portable digital media, backup media, and in logs).	UniTerm never stores cardholder data, nor does it have its own logging facilities.
Protect keys used to secure cardholder data against disclosure and misuse.	UniTerm never stores cardholder data and therefore does not utilize keys.
Implement key-management processes and procedures for cryptographic keys used for encryption of cardholder data.	UniTerm never stores cardholder data and therefore does not utilize keys.
Implement secure key-management functions.	UniTerm never stores cardholder data and therefore does not utilize keys.
Provide a mechanism to render irretrievable cryptographic key material or cryptograms stored by the payment application.	UniTerm never stores cardholder data and therefore does not utilize keys.
Use unique user IDs and secure authentication for	UniTerm does not provide or facilitate administrative access.

administrative access and access to cardholder data.	
Use unique user IDs and secure authentication for access to PCs, servers, and databases with payment applications.	UniTerm does not provide or facilitate administrative or remote access.
Implement automated audit trails.	UniTerm does not provide its own logging facilities, instead all requests are sent to Monetra which logs and maintains the audit trails on behalf of UniTerm.
Facilitate centralized logging.	Since UniTerm sends all requests and metadata to Monetra, Monetra is responsible for facilitating centralized logging.
Implement and communicate application versioning methodology.	Please see the Versioning section.
Securely implement wireless technology.	UniTerm is not designed to use or facilitate the use of wireless technologies.
Secure transmissions of cardholder data over wireless networks.	UniTerm is not designed to use or facilitate the use of wireless technologies.
Provide instructions for secure use of wireless technology.	Integrators should ensure they secure any wireless technologies in use in compliance with the requirements in PA-DSS Requirement 6.3
Use only necessary and secure services, protocols, components and dependent software and hardware, including those provided by third parties.	UniTerm communicates only via SSL/TLS using proprietary protocols.
Store cardholder data only on servers not connected to the Internet	UniTerm never stores cardholder data.
Implement two-factor authentication for all remote access to payment application that originates from outside the customer environment.	UniTerm never stores cardholder data, nor does it provide access to cardholder data. Integrators must ensure that all remote access originating from outside the customer's network to a payment application (Monetra) must use two-factor authentication.
Securely deliver remote payment application updates.	Integrators must securely deliver updates to UniTerm in compliance with the Deployment section. Deployments must be done in accordance with the PCI PA-DSS requirement 10.3.
Securely implement remote-access software.	Main Street Softworks will never reach out to a remote customer network. If an Integrator chooses to support remote

	access for management they must do so in compliance with PA-DSS Requirement 10.3.2.
Secure transmissions of cardholder data over public networks.	UniTerm communicates only via SSL/TLS using proprietary protocols.
Encrypt cardholder data sent over end-user messaging technologies.	UniTerm does not facilitate or support the use of end-user messaging technologies.
Encrypt non-console administrative access.	UniTerm does not provide or facilitate administrative access.